
Blender-Addon-Photogrammetry- Importer

Release 2.0.0

Sebastian Bullinger

Aug 31, 2023

CONTENTS

1	Getting Started	3
2	Example Results (Shipped with Addon)	65
	Python Module Index	67
	Index	69

This documentation describes an [addon for Blender](#) that allows to import different reconstruction results of several [Structure from Motion](#) and [Multi-View Stereo](#) libraries.

Supported libraries (data formats):

- [Colmap](#) (Model folders (BIN and TXT), workspaces, NVM, PLY)
- [Meshroom](#) (MG, JSON, SfM, PLY)
- [MVE](#) (MVE workspaces) ¹
- [Open3D](#) (JSON, LOG, PLY) ¹
- [OpenSfM](#) (JSON)
- [OpenMVG](#) (JSON, NVM, PLY) ²
- [Regard3D](#) (OpenMVG JSON)
- [VisualSfM](#) (NVM) ¹

In addition, the addon supports some common point cloud data formats:

- [Polygon files](#) (PLY) ³
- [Point Cloud Library files](#) (PCD) ³
- [LASer files](#) (LAS) ^{3,4}
- [LASzip files](#) (LAZ) ^{3,4,5}
- [Simple ASCII point files](#) (ASC, PTS, CSV) ³

¹ Requires [pillow](#) to read image sizes from disk. ² Requires [pillow](#) for point color computation.

³ Requires [pyntcloud](#) for parsing. ⁴ Requires [laspy](#) for parsing. ⁵ Requires [lazrs](#) for parsing.

The latest release of the addon is currently compatible with Blender 3.1.2 onwards. For older Blender versions you might find a suitable release [here](#).

GETTING STARTED

1.1 Installation Instructions

1.1.1 Delete any Previous Version of the Addon

- **Remove any previous version of the addon from Blender.**
 - Inside Blender go to Edit/Preferences/Add-ons, search for Import-Export: Photogrammetry Import Export Addon and click on Remove
 - See the *troubleshooting page* for more information.
- **THEN, CLOSE BLENDER**
- Reopen Blender and follow the installation instructions below

Without removal of previous versions errors may appear during activation or Blender may not reflect the latest changes of the addon.

1.1.2 Download the Addon for Blender 2.80 (or newer)

Option 1: Download a Release Version of the Addon

Download the corresponding `photogrammetry_importer.zip` from the [release page](#).

Option 2: Download the Latest Version of the Addon

For example, clone the addon with

```
git clone https://github.com/SBCV/Blender-Addon-Photogrammetry-Importer.git
```

(Alternatively, go to <https://github.com/SBCV/Blender-Addon-Photogrammetry-Importer>, click on clone or download, and download the archive by clicking on Download Zip. Extract the `Blender-Addon-Photogrammetry-Importer-master.zip` file, which creates a folder `Blender-Addon-Photogrammetry-Importer`.)

Finally, compress the folder `photogrammetry_importer` in `Blender-Addon-Photogrammetry-Importer` to a zip archive `photogrammetry_importer.zip`. The final structure must look as follows:


```
photogrammetry_importer.zip /
  photogrammetry_importer /
    blender_utility
    ext
    file_handler
    ...
    __init__.py
```

For convenience the repository contains a script (`create_blender_addon_zip.sh` for Linux, `create_blender_addon_zip.bat` for Windows) that creates the required `photogrammetry_importer.zip` file. Run the script without parameters (e.g. `./create_blender_addon_zip.sh`).

1.1.3 Install the Addon

Install the addon by

- Opening the preferences of Blender (Edit / Preferences ...)
- Select Add-ons in the left toolbar
- Click on Install... in the top toolbar
- Navigate to the `photogrammetry_importer.zip` file, select it and click on Install Add-on
- Scroll down to **ACTIVATE the addon**, i.e. check the bounding box left of Import-Export: Photogrammetry Import Export Addon (see image below)




Follow the instructions on the [customize](#) page, to adjust the default options of the addon.

1.1.4 Install Optional Dependencies

This addon uses [Pillow](#) to read the (missing) image sizes from disk - required by the MVE, the Open3D and the VisualSFM importer. Pillow is also used to compute the (missing) point colors for OpenMVG JSON files. Using Pillow instead of Blender's image API significantly improves processing time. Furthermore, this addon uses [Pyntcloud](#) to import several point cloud formats such as .ply, .pcd, .las, .laz, .asc, .pts and .csv. For parsing .las and .laz files [Laspy 2.0 \(or newer\)](#), [Lazrs](#) and [Pyntcloud 0.3 \(or newer\)](#) is required.

Option 1: Installation using the GUI (recommended)

Requires Blender 2.83.5 or newer. **Administrator privileges might be required to install the dependencies (depending on the location of the Blender installation directory).**



Clicking on **Download and Install Optional Dependencies** installs `pip` (if not already present) and uses the `pip` executable to install the actual dependencies. Start Blender from the command line to see the installation progress and potential error messages.

Note: If you experience problems while *updating* the dependencies, try a fresh Blender installation.

Note: If you use [VSCode](#) with [Blender VSCode](#) to run this addon, the installation of `laspy` will fail. In this case you need to install it manually (see below).

Option 2: Installation using the command line

In case the installation using the GUI does not work, it is possible to install the dependencies with the command line. If you haven't installed [pip](#) for Blender already, download <https://bootstrap.pypa.io/get-pip.py> and copy the file to

```
<Blender_Root>/<Version>/python/bin
```

For Linux run:

```
<Blender_Root>/<Version>/python/bin/python3.7m <Blender_Root>/<Version>/python/bin/get-  
↵pip.py  
<Blender_Root>/<Version>/python/bin/pip install pillow  
<Blender_Root>/<Version>/python/bin/pip install lazrs  
<Blender_Root>/<Version>/python/bin/pip install laspy  
<Blender_Root>/<Version>/python/bin/pip install pyntcloud
```

For Windows run:

```
<Blender_Root>/<Version>/python/bin/python.exe <Blender_Root>/<Version>/python/bin/get-  
↵pip.py  
<Blender_Root>/<Version>/python/Scripts/pip.exe install pillow  
<Blender_Root>/<Version>/python/Scripts/pip.exe install lazrs  
<Blender_Root>/<Version>/python/Scripts/pip.exe install laspy  
<Blender_Root>/<Version>/python/Scripts/pip.exe install pyntcloud
```

IMPORTANT: Use the full path to the python and the pip executable. Otherwise the system python installation or the system pip executable may be used.

1.2 Troubleshooting

1.2.1 Known (Blender) Issues

Please see [this issue](#) for an up-to-date list of limitations.

1.2.2 Problems to Activate the Addon

If you experience problems while installing and activating a newer version of the addon (i.e. an older version of the addon was previously installed), delete Blender's user folder of the addon. [This page](#) of the Blender manual provides information about the location of the corresponding folder.

Make sure that you CLOSE Blender BEFORE deleting the folder.

Windows

Under Windows delete the following folder:

```
%USERPROFILE%\AppData\Roaming\Blender Foundation\Blender\<Version>\scripts\addons\  
↪ photogrammetry_importer
```

In the case of Blender 2.82:

```
%USERPROFILE%\AppData\Roaming\Blender Foundation\Blender\2.82\scripts\addons\  
↪ photogrammetry_importer
```

Linux

Under Linux delete:

```
~/ .config/blender/<Version>/scripts/addons/photogrammetry_importer`
```

In the case of Blender 2.82:

```
~/ .config/blender/2.82/scripts/addons/photogrammetry_importer
```


1.2.3 Blender Crashes while Importing Reconstructions

This is probably not an issue of the addon or Blender, but caused by outdated graphic drivers. If the problem persists (after restarting Blender / the operating system), one can find more information in the [Blender manual](#). As workaround one may import the point cloud as Blender object or as a particle system (by adjusting the corresponding import options) instead of drawing the point cloud with OpenGL (which is the default import option).

1.3 Customize Import/Export Options


1.3.1 Enable / Disable Importers and Exporters

If you want to only add a subset of the provided import/export functions, adjust the checkboxes in the *Addon preferences* and click on the Update (Enable/Disable) Importers and Exporters button as shown below:



1.3.2 Adjusting Default Import Options

Furthermore, it is possible to set the default import options by adjusting the corresponding settings in the *Addon Preferences* - see the image below.



1.4 Examples

This repository contains under `Blender-Addon-Photogrammetry-Importer/examples` several reconstruction results of the following Structure from Motion libraries:

- Colmap (colmap_example_model_bin and colmap_example_model_txt)
- Meshroom (meshroom_example.json)
- OpenMVG (OpenMVG_example.json)
- VisualSfM (VisualSfM_example.nvm)

If you want to show the corresponding images in Blender, download the corresponding [dataset](#) and copy the images to


Blender-Addon-Photogrammetry-Importer/examples/images. Alternatively, you can adjust the corresponding path in the import options of the addon.

1.5 Import Data

Errors, help and logging information during import / export is shown in the `Info` area. Check this output, if nothing is imported. Probably the default width and height values are not set (see below).

1.5.1 General

In Blender use File/Import/<Import Function> to import the corresponding file.



For each camera one can add the corresponding image plane. Pillow is required to read the images from disc. Use the import dialog to adjust the image path. By default the addon searches for the images in the folder where the reconstruction file is located. **This addon uses the node system of Cycles to visualize the image planes. Thus, the addon switches automatically to Cycles, if image planes are added.**

There is an option to represent the point cloud with a particle system. This allows you to render the point cloud. A single texture is used to store the color of all particles. **The color of the points / textures of the images are visible, if “Cycles Render” is selected and the 3D view is set to “Material”.** Eevee does not (yet) support particle info

nodes. (Checkout the [manual](#) for more information.) Thus, it is currently **not possible** to render point clouds with individual particle colors **in Eevee**.

1.5.2 VisualSfM


The addon automatically looks for the fixed calibration line in the NVM file (i.e. NVM_V3 FixedK fx cx fy cy r (first line)). Without the fixed calibration line the addon assumes that the principal point is at the image center. NVM files contain no information about the size of the images. Use the import dialog to adjust the image path to automatically read the image size from disc or set the default width and height values.

1.5.3 OpenMVG JSON

The OpenMVG JSON files contain no color information. If you want to import a point cloud with color information, you might want to use the `openMVG_main_ComputeSfM_DataColor` tool (see [this link](#)) and import the corresponding *.ply file.

1.5.4 Meshroom

By default Meshroom stores the Structure from Motion results (i.e. cameras and points) in Alembic (*.abc) files. Since parsing *.abc files requires building additional (heavy) dependencies, e.g. [this library](#), it is currently not supported by this addon. However, one can add a `ConvertSfMFormat` node in Meshroom (see image below) to write the reconstruction result to *.SfM / *.json files.



In addition to *.SfM / *.json files the addon allows to import *.mg files, which allows to also import corresponding meshes. The addon prioritizes the output of recently added nodes (e.g. `ConvertSfMFormat3` has a higher priority than `ConvertSfMFormat`). For importing meshes the addon uses the following prioritization: first the output of `Texturing`, then the output of `Meshfiltering` and finally the output of `Meshing`. **After adding the nodes (e.g. `ConvertSfMFormat`), do not forget to save your project (i.e. the *.mg file),** since the addon uses this file to determine available reconstruction results.

In order to import the original images corresponding to the *.mg file, one can set the import option `Image File Path Type` of the Blender-Addon to `Absolute Path`. To import the undistorted *.exr images set `Image File Path Type` to `File Name` and set `Image Directory` to the folder with the *.exr files.

1.5.5 Regard3D

By default Regard3D stores the Structure from Motion results in `path/to/project/pictureset_0/matching_0/triangulation_0/sfm_data.bin`. Use [OpenMVG](#) to convert the *.bin to a *.json file with `openMVG_main_ConvertSfM_DataFormat -i path/to/sfm_data.bin -o path/to/cameras.json`. For Windows you can find the pre-built binaries of OpenMVG [here](#).

1.5.6 ASCII

Each line in an ASCII file (`.asc/.pts/.csv`) represents a point with several attributes (coords, normals, colors, ...). In the case of `.asc/.pts/` there might be an optional header such as `//X Y Z Rf Gf Bf Intensity` or `//X Y Z Intensity R G B` that defines the order of the attributes. If no header is provided, the addon tries to estimate the order of the attributes. The color attributes can be defined as integer values (R G B) between 0 and 255 or float values (Rf Gf Bf) between 0.0 and 1.0. Attributes other than position and color are ignored by the addon.

1.5.7 Meshes

In order to view a reconstructed mesh with the corresponding sparse reconstruction (cameras and point cloud) import the files separately. When importing *.obj files make sure to adjust the corresponding import transform options. Set the Forward option to Y Forward and the Up option to Z Up.

1.5.8 Limitations

Blender supports only global render settings (which define the ratio of all cameras). If the reconstruction file contains cameras with different aspect ratios, it is not possible to visualize the camera cones correctly. Furthermore, radial distortions of the camera model used to compute the reconstruction will result in small misalignment of the cameras and the particle system in Blender.

1.6 Export Data

Errors, help and logging information during export is shown in the “Info” area.

The addon allows to export camera poses and vertex positions to a few photogrammetry formats. Currently, the addon supports:


- Colmap model folders
- NVM files of VisualSFM

Select all cameras and objects you want to export. For each selected mesh the vertices are stored as points in the output file/folder. Use `File/Export/<Export Function>` to export the corresponding file.


1.7 Scale Cameras and Points

1.7.1 Adjust the Scale of Cameras after Importing


1.) Select the cameras and the corresponding image planes, i.e. right click on the collection Camera Image Plane Pair Collection and in the context menu on Select Objects.



2.) Select the individual origins as pivot points, i.e. click in the 3D view on Pivot Point and select Individual Origins.




3.) Scale the objects, i.e. press s and move the mouse or press s and enter the scaling factor.




1.7.2 Adjust the Scale of OpenGL Points Drawn in the 3D View (After Importing)

The size of the points in the OpenGL point cloud can be defined using the panel in the 3D view.




1.7.3 Adjust the Scale/Shape of Geometry Node Points of a Mesh Object (After Importing)

The input of the Geometry Nodes (i.e. point radius and the point subdivision) can be adjusted using the Properties editor (Shift + F7).




1.8 Alignment of Cameras and Point Cloud

The 3D viewport of Blender unfortunately does not support radial camera distortions. If the imported Structure from Motion reconstruction has a camera model with radial distortion, the image planes and background images will not perfectly align with the 3D point cloud. For example, such cases occur if the intrinsic camera parameters are optimized (not fixed) during the Structure from Motion reconstruction. The following image shows a corresponding example. For instance, see the offset between the points at the left and the right side of the building.




There are two ways to address this issue.

Option 1: This approach is only applicable, if the images are not subject to radial distortion. Provide the (true) intrinsic camera parameters and fix/lock these during reconstruction. The following image shows the corresponding result.




Option 2: After computing the Structure from Motion reconstruction perform the first step (i.e. image undistortion) of the dense reconstruction (Multi-View Stereo). Using the undistorted images instead of the original imagery resolves the alignment problem. For example, Colmap and Meshroom allow to compute undistorted images. An example is shown below.



1.9 Visualization and Rendering

Currently, this addon supports the following two point cloud visualization options:


- Representing the points with a mesh object (using Blender's Geometry Nodes)
- Visualizing the points with OpenGL




Each option has different advantages / disadvantages.

1.9.1 Option 1: Representing the Points with a Mesh Object (using Blender's Geometry Nodes)

If selected, the addon adds a blender object with a vertex for each point in the point cloud. The option Add Geometry Nodes create several geometry nodes (see image below) that allow to render the point cloud with Eevee or Cycles.




The point radius and the point subdivision can be adjusted after import using the Properties editor (Shift + F7).



1.9.2 Option 2: Visualizing and rendering the points with OpenGL

If selected, the point cloud is shown in the Viewport using Blender's OpenGL API. That means, there is **no** Blender object representing the points in the point cloud. The pose (i.e. rotation and translation) of the object can be changed by adjusting the corresponding "anchor" (i.e. a Blender **empty** object).

- Advantage: Low computational costs for visualization.
- Disadvantage: It is not possible to render these points with the render functions provided by Blender. However, this addon provides a panel to save/export OpenGL renderings of the points using an offscreen buffer or Blender's screenshot operator (see image below).




Option 2a: Write results to disk with Blender's offscreen buffer

Rendering the scene with Blender's offscreen buffer renders (only!) the points drawn with Blender's OpenGL API to disk. In order to render other elements such as cameras, image planes, meshes etc use Blender's screenshot operator - see below.


Option 2b: Write results to disk with Blender's screenshot operator

Since Blender's screenshot operator renders all visible elements of the viewport to disk it is usually convenient to adjust the appearance.


In order to hide gridlines, axes etc. click on the **Overlays** button in Blender's 3D viewport and disable the corresponding options - see the image below.



To ensure that the reconstruction results are not occluded by Blender panels go to **Edit / Preferences ...** and uncheck the option **Region Overlap** - as shown in the following image. There, it is also possible to hide the **Navigation Controls**.



After adjusting these options the viewport looks as follows.



1.10 Addon Usage with Python

There are two ways to access the functionality of the addon with Blender's Python console / text editor (after installation and activation of the addon):

- Import the addon as Python module
- Call the appropriate operator registered in `bpy.ops.import_scene`

1.10.1 Option 1: Import the addon as Python module

According to the [documentation](#):

The only difference between addons and built-in Python modules is that addons must contain a `bl_info` variable

Therefore, after installation and activation one can use Python's standard import syntax to import different classes and functions such as:

```
from photogrammetry_importer.types.camera import Camera
from photogrammetry_importer.file_handlers.colmap_file_handler import ColmapFileHandler
from photogrammetry_importer.importers.point_utility import add_points_as_mesh_vertices
```

Example 1: Add points contained in a ply file as a particle system.

```

import bpy
from photogrammetry_importer.file_handlers.point_data_file_handler import PointDataFileHandler
from photogrammetry_importer.blender_utility.object_utility import add_collection
from photogrammetry_importer.importers.point_utility import add_points_as_mesh_vertices

ifp = "path/to/Blender-Addon-Photogrammetry-Importer/examples/Example.ply"
points = PointDataFileHandler.parse_point_data_file(ifp)
reconstruction_collection = add_collection("Reconstruction Collection")
add_points_as_mesh_vertices(
    points,
    reconstruction_collection=reconstruction_collection,
    add_mesh_to_point_geometry_nodes=True,
    point_radius=0.05,
    point_subdivisions=1,
    add_color_as_custom_property=True,
)
# Optionally, change the shading type to show the particle colors
area = next(area for area in bpy.context.screen.areas if area.type == "VIEW_3D")
space = next(space for space in area.spaces if space.type == "VIEW_3D")
space.shading.type = "RENDERED"

```

Example 2: Use the intrinsic and extrinsic parameters of each reconstructed camera to render the corresponding point cloud via an off screen buffer to disk.

```

import os
from photogrammetry_importer.file_handlers.colmap_file_handler import ColmapFileHandler
from photogrammetry_importer.types.point import Point
from photogrammetry_importer.blender_utility.object_utility import add_collection
from photogrammetry_importer.importers.camera_utility import add_camera_object
from photogrammetry_importer.opengl.utility import render_opengl_image
from photogrammetry_importer.blender_utility.image_utility import save_image_to_disk

# Make sure you've downloaded the corresponding images (i.e. the sceaux castle dataset)
model_idp = "path/to/Blender-Addon-Photogrammetry-Importer/examples/colmap_example_model_
↳bin"
image_idp = "path/to/Blender-Addon-Photogrammetry-Importer/examples/images"
odp = "path/to/output"

# Parse the reconstruction
cameras, points3D = ColmapFileHandler.parse_colmap_model_folder(model_idp, image_idp,
↳image_fp_type="NAME")
coords, colors = Point.split_points(points3D)

# Render the point cloud for reach camera
camera_collection = add_collection("Camera Collection")
render_img_name = "render_result"
for cam in cameras:
    cam_name = cam.get_file_name()
    print(f"Camera: {cam_name}")
    ofp = os.path.join(odp, cam_name)

    camera_object = add_camera_object(cam, cam_name, camera_collection)

```

(continues on next page)

(continued from previous page)

```

        render_opengl_image(render_img_name, camera_object, coords, colors, point_
↪size=10)
        save_image_to_disk(render_img_name, ofp, save_alpha=False)

```

Example 3: Use the animated camera to render the point cloud with Cycles.

```

import os
import bpy
from photogrammetry_importer.file_handlers.colmap_file_handler import ColmapFileHandler
from photogrammetry_importer.blender_utility.object_utility import add_collection
from photogrammetry_importer.importers.point_utility import add_points_as_object_with_
↪particle_system
from photogrammetry_importer.importers.camera_animation_utility import add_camera_
↪animation
from photogrammetry_importer.importers.camera_utility import adjust_render_settings_if_
↪possible

# Make sure you've downloaded the corresponding images (i.e. the sceaux castle dataset)
model_idp = "path/to/Blender-Addon-Photogrammetry-Importer/examples/colmap_example_model_
↪bin"
image_idp = "path/to/Blender-Addon-Photogrammetry-Importer/examples/images"
odp = "path/to/output"

# Parse the reconstruction
cameras, points3D = ColmapFileHandler.parse_colmap_model_folder(model_idp, image_idp,
↪image_fp_type="NAME")

# Add the reconstruction results
reconstruction_collection = add_collection("Reconstruction Collection")
add_points_as_object_with_particle_system(points3D, reconstruction_collection, point_
↪extent=0.02)
animated_camera_object = add_camera_animation(cameras, reconstruction_collection)

# Adjust the render settings and render animation with Cycles
adjust_render_settings_if_possible(cameras)
bpy.context.scene.render.engine = "CYCLES"
bpy.context.scene.cycles.device = "GPU"
bpy.context.scene.render.filepath = os.path.join(odp, "")
bpy.context.scene.camera = animated_camera_object
bpy.ops.render.render(animation=True)

```

1.10.2 Option 2: Call the appropriate operator registered in bpy.ops.import_scene

In Blender open the Python Console and use Tabulator to list the available operators with corresponding parameters, i.e.

```

>>> bpy.ops.import_scene.<TABULATOR>
>>> bpy.ops.import_scene.
        colmap_model(
        fbx(
        gltf(

```

(continues on next page)

(continued from previous page)

```

meshroom_sfm_json(
mve_folder(
obj(
open3d_log_json(
openmvg_json(
opensfm_json(
point_data(
visualsfm_nvm(
x3d(

```

Or use Tabulator with a specific function, e.g. `point_data()`, to show the corresponding parameters.

```

>>> bpy.ops.import_scene.point_data(<TABULATOR>
>>> bpy.ops.import_scene.point_data(
point_data()
bpy.ops.import_scene.point_data(
    import_points=True,
    point_cloud_display_sparsity=1,
    draw_points_with_gpu=True,
    add_points_to_point_cloud_handle=True,
    add_points_as_particle_system=False,
    mesh_type='CUBE',
    point_extent=0.01,
    add_particle_color_emission=True,
    set_particle_color_flag=False,
    particle_overwrite_color=(0, 1, 0),
    add_points_as_mesh_object=False,
    adjust_clipping_distance=False,
    filepath="",
    directory="",
    filter_glob="*.ply;*.pcd;*.las;*.laz;*.asc;*.pts;*.csv")

```

1.10.3 Python Scripting with Blender

VS Code with this [extension](#) has many advantages over Blender's built-in text editor. [Here](#) is an introduction / tutorial video.

Note: When using VS Code to start Blender with a specific addon for the first time, it is sometimes necessary to run the command twice (i.e. within VS Code run `ctrl+shift+p / Blender: Start / path_to_Blender_executable`, then close Blender, then run `ctrl+shift+p / Blender: Start / path_to_Blender_executable` again).

1.11 Extending the Addon

The addon follows a modular approach to simplify the extensibility of additional libraries. Each supported library requires the implementation of a corresponding *FileHandler* and *ImportOperator* - see the figure below. The *FileHandler* parses library specific file formats or directory structures and returns library agnostic information of cameras, points and meshes. The *ImportOperator* may use different classes provided by the framework (e.g. *CameraImporter*, *PointImporter* and *MeshImporter*) to define the required import options and to import the reconstruction extracted by the *FileHandler*.

Fig. 1: Integration of the addon with Blender - illustrated with the Colmap importer. In order to support additional SfM and MVS libraries it is sufficient to implement the corresponding import operators and file handlers. To simplify the figure only relevant classes and methods are shown.

1.12 Contribution

I am always happy to get advices as well as feature and pull requests. If you want to create a pull request, I recommend to use [VS Code](#) with this [extension](#). This allows to perform fast development and validation cycles with Blender scripts and addons. [Here](#) is an introduction / tutorial video.

This addon relies on [Black](#) for formatting. To ensure that your Pull Request is correctly formatted perform the following steps:

- Install Black - checkout the [installation instructions](#)
 - `cd path/to/Blender-Addon-Photogrammetry-Importer`
 - `black --line-length 79 --exclude`
- ```
photogrammetry_importer/ext
photogrammetry_importer
• black --line-length 79
doc/sphinx/source/conf.py
```

The addon uses Docstrings for documentation - see [PEP 257](#) and [PEP 287](#).

### 1.13 Documentation

The addon uses [Sphinx](#), [sphinx\\_rtd\\_theme](#), [sphinx-autoapi](#) to generate the documentation.

These tools can be installed with

- `pip install -U sphinx`
- `pip install sphinx-rtd-theme`
- `pip install sphinx-autoapi`

In order to build the documentation locally

- download the [project](#)
- navigate to the `sphinx` folder (i.e. `cd Blender-Addon-Photogrammetry-Importer/doc/sphinx`)
- run `make html / make latex` (using Linux) or `make.bat html / make.bat latex` (using Windows)

### 1.14 Recent Features / Changelog

Changelog with most relevant features. Recently added features are listed at the top of this page.



### 1.14.1 2022

- Fix geometry node creation for Blender 3.2.1
- Add support for installation and removal of individual dependencies
- Fix the point exporter for OpenGL point clouds
- Remove the particle system based point cloud representation method (because of the new point cloud representation option based on geometry nodes)
- Add particle colors to geometry nodes (Thanks to @Linusnie)
- Add a new point cloud representation method based on geometry nodes. Allows to render the point cloud with Eevee and Cycles
- Replace pylas with laspy ( $\geq 2.0$ )
- Add an option to center points around the origin (useful for laz/las files)
- Remove the point color computation for OpenMVG json files, due to a bug in pillow caused by the blender python environment
- Adjust the screenshot rendering functionality according to api changes of Blender 3.0
- Replacing the bgl module with the gpu module to fix the offscreen rendering of point clouds under windows
- Fix the dependency installation for Blender 2.8 - 2.91 of the newly introduced dependency manager

### 1.14.2 2021

- Improve management of dependency installation and corresponding GUI options
- Made point sizes of point clouds and depth maps (drawn with OpenGL) persistent
- Changed the usage of draw handlers to avoid potential crashes when deleting the point cloud anchor objects
- Made depth maps persistent (i.e. the corresponding information is stored in the blend file)
- Added features to export images of the imported reconstructions including cameras, background images, image planes, point clouds and meshes

### 1.14.3 2020

- Reorganized (persistent) addon preferences
- Added an option to use the undistorted images contained in the workspaces of the Colmap, Meshroom and MVE
- Added several python examples that demonstrate the API usage
- Added vertex colors to the mesh shader nodes to improve the visibility of the corresponding mesh
- Added background images for the animated camera
- Added code to automatically generate the API Documentation with autoapi
- Fixed an incorrect offset in the texture coordinate computation of the particle system
- Added a workaround to circumvent a bug in Blender, which appears only for large particle systems (T81103)
- Added GUI elements to install/uninstall the dependencies (Pillow, Pyntcloud)
- Addon uses now the Pyntcloud library to import PLY, PCD, LAS, ASC, PTS and CSV files
- Added an option to import depth maps of MVE workspaces

- Added an option to import depth maps of Colmap as point clouds
- Added support for MVE workspaces
- Added addon preferences to configure the import/export default settings
- Added addon preferences to enable/disable importers and exporters
- Added an OpenSfM importer
- OpenGL data is now persistent (stored in blend file) and is available after reopening
- Added a panel with options to export renderings of the point cloud using OpenGL
- Added support for Colmap dense workspaces
- Added support for Meshroom projects (.mg files)
- Fixed occlusion of point clouds drawn with OpenGL
- Added a Colmap exporter
- Added an Open3D importer
- Added an option to render point clouds with OpenGL
- Added support for absolute and relative paths in reconstruction results
- Added a preset possibility for each importer to customize default import options

### 1.14.4 2019

- Added support to import undistorted images of Colmap/Meshroom
- Fixed a bug leading to incorrect principal points
- Added option to remove discontinuities in animations
- Added an option to show source images as Blender background images
- Added particle emission to improve visibility
- Added importers for Colmap, OpenMVG and Meshroom
- Compatibility fix for Blender 2.8

### 1.14.5 2018

- Added an option to add camera animation
- Added an option to import images as image planes
- Added an exporter for cameras and mesh vertex positions as NVM
- Added an option to represent point clouds with particle systems

### 1.14.6 2017

- Added a NVM importer
- Initial Commit

## 1.15 API Reference

This page contains auto-generated API reference documentation<sup>1</sup>.

### 1.15.1 photogrammetry\_importer

A Blender addon to import different photogrammetry formats.

#### Subpackage Summary

**ext**

External dependencies.

**file\_handlers**

Classes to read and write different file formats.

**operators**

Operators to import and export different file formats into Blender.

**panels**

GUI elements to adjust and leverage the imported objects.

**preferences**

Persistent addon preferences.

**properties**

Properties used by the import and export operators.

**registration**

Registration of the import and export operators.

**types**

Types used by different subpackages.

**utility**

General and Blender-specific utility functions.

#### Subpackages

**photogrammetry\_importer.blender\_utility**

Contains Blender-specific utility functions.

---

<sup>1</sup> Created with `sphinx-autoapi`

### Submodules

`photogrammetry_importer.blender_utility.image_utility`

#### Module Contents

`photogrammetry_importer.blender_utility.image_utility.save_image_to_disk`(*image\_name*,  
*file\_path*,  
*save\_alpha=True*)

Save a Blender image to disk.

`photogrammetry_importer.blender_utility.logging_utility`

#### Module Contents

`photogrammetry_importer.blender_utility.logging_utility.log_report`(*output\_type*, *some\_str*,  
*op=None*)

Write a string to the console and to Blender's info area.

`photogrammetry_importer.blender_utility.object_utility`

#### Module Contents

`photogrammetry_importer.blender_utility.object_utility.add_empty`(*empty\_name*, *collection=None*)

Add an empty to the scene.

`photogrammetry_importer.blender_utility.object_utility.add_obj`(*data*, *obj\_name*,  
*collection=None*)

Add an object to the scene.

`photogrammetry_importer.blender_utility.object_utility.add_collection`(*collection\_name*, *parent\_collection=None*)

Add a collection to the scene.

`photogrammetry_importer.blender_utility.retrieval_utility`

#### Module Contents

`photogrammetry_importer.blender_utility.retrieval_utility.get_selected_object`()

Get the selected object or return None.

`photogrammetry_importer.blender_utility.retrieval_utility.get_selected_empty`()

Get the selected empty or return None.

`photogrammetry_importer.blender_utility.retrieval_utility.get_selected_camera`()

Get the selected camera or return None.

`photogrammetry_importer.blender_utility.retrieval_utility.get_scene_animation_indices`()

Get the animation indices of the scene.

`photogrammetry_importer.blender_utility.retrieval_utility.get_object_animation_indices(obj)`  
Get the animation indices of the object.

## `photogrammetry_importer.file_handlers`

Contains classes to read and write different file formats.

### Submodules

#### `photogrammetry_importer.file_handlers.colmap_file_handler`

### Module Contents

**class** `photogrammetry_importer.file_handlers.colmap_file_handler.ColmapFileHandler`

Class to read and write Colmap models and workspaces.

**static** `parse_colmap_model_folder(model_idp, image_dp, image_fp_type, depth_map_idp=None, suppress_distortion_warnings=False, op=None)`

Parse a Colmap model.

**static** `parse_colmap_folder(idp, use_workspace_images, image_dp, image_fp_type, suppress_distortion_warnings=False, op=None)`

Parse a Colmap model or a Colmap workspace.

**static** `write_colmap_model(odp, cameras, points, op=None)`

Write cameras and points as Colmap model.

#### `photogrammetry_importer.file_handlers.image_file_handler`

### Module Contents

**class** `photogrammetry_importer.file_handlers.image_file_handler.ImageFileHandler`

Class to read and write images using Pillow.

**PILImage**

**classmethod** `read_image_size(image_ifp, default_width, default_height, op=None)`

Read image size from disk.

#### `photogrammetry_importer.file_handlers.meshroom_file_handler`

### Module Contents

**class** `photogrammetry_importer.file_handlers.meshroom_file_handler.MeshroomFileHandler`

Class to read and write Meshroom files and workspaces.

```
classmethod parse_meshroom_sfm_file(sfm_ifp, image_idp, image_fp_type,
 suppress_distortion_warnings, op=None)
```

Parse a Meshroom (.sfm or .json) file.

Parse different file formats created with the StructureFromMotion / ConvertSfMFormat node in Meshroom.

```
classmethod parse_meshroom_mg_file(mg_fp, sfm_node_type, sfm_node_number, mesh_node_type,
 mesh_node_number, prepare_node_number, op=None)
```

Parse a Meshroom project file (.mg).

```
classmethod parse_meshroom_file(meshroom_ifp, use_workspace_images, image_dp, image_fp_type,
 suppress_distortion_warnings, sfm_node_type, sfm_node_number,
 mesh_node_type, mesh_node_number, prepare_node_number,
 op=None)
```

Parse a Meshroom file.

Supported file formats are .mg, .sfm or .json.

## **photogrammetry\_importer.file\_handlers.mve\_file\_handler**

### **Module Contents**

```
class photogrammetry_importer.file_handlers.mve_file_handler.MVEFileHandler
```

Class to read and write MVE workspaces.

```
static parse_synth_out(synth_out_ifp)
```

Parse the synth\_0.out file in the MVE workspace.

```
static parse_meta(meta_ifp, width, height, camera_name, op)
```

Parse a meta.ini file in the MVE workspace.

```
static parse_views(views_idp, default_width, default_height, add_depth_maps_as_point_cloud,
 op=None)
```

Parse the views directory in the MVE workspace.

```
static parse_mve_workspace(workspace_idp, default_width, default_height,
 add_depth_maps_as_point_cloud, suppress_distortion_warnings,
 op=None)
```

Parse a MVE workspace.

```
static read_depth_map(depth_map_ifp)
```

Read a depth map.

## **photogrammetry\_importer.file\_handlers.open3D\_file\_handler**

### **Module Contents**

```
class photogrammetry_importer.file_handlers.open3D_file_handler.Open3DFileHandler
```

Class to read and write Open3D files.

**static parse\_open3d\_file**(*open3d\_ifp, image\_dp, image\_fp\_type, op*)

Parse an Open3D (.json or .log) file.

The .json format supports intrinsics as well as extrinsic parameters, whereas the .log (Redwood) format contains only extrinsic parameters.

**photogrammetry\_importer.file\_handlers.openmvg\_json\_file\_handler**

### Module Contents

**class**

**photogrammetry\_importer.file\_handlers.openmvg\_json\_file\_handler.OpenMVGJSONFileHandler**

Class to read and write OpenMVG files.

**static parse\_openmvg\_file**(*input\_openMVG\_file\_path, image\_dp, image\_fp\_type, suppress\_distortion\_warnings, op=None*)

Parse an OpenMVG (.json) file.

**photogrammetry\_importer.file\_handlers.opensfm\_json\_file\_handler**

### Module Contents

**class**

**photogrammetry\_importer.file\_handlers.opensfm\_json\_file\_handler.OpenSfMJSONFileHandler**

Class to read and write OpenSfM files.

**static parse\_opensfm\_file**(*input\_opensfm\_fp, image\_dp, image\_fp\_type, reconstruction\_idx, suppress\_distortion\_warnings=False, op=None*)

Parse a OpenSfM (.json) file.

**photogrammetry\_importer.file\_handlers.point\_data\_file\_handler**

### Module Contents

**class photogrammetry\_importer.file\_handlers.point\_data\_file\_handler.PointDataFileHandler**

Class to read and write common point data files.

**static parse\_point\_data\_file**(*ifp, op=None*)

Parse a point data file.

Supported file formats are: .ply, .pcd, .las, .laz, .asc, .pts and .csv.

Relies on the pyntcloud, the laspy and/or the lazrs library to parse the different file formats.

`photogrammetry_importer.file_handlers.transformation_file_handler`

## Module Contents

`class photogrammetry_importer.file_handlers.transformation_file_handler.TransformationFileHandler`

Class to read directories with files storing transformations.

**static** `parse_transformation_folder(t_idp, op=None)`

Parse a directory with files storing transformations.

`photogrammetry_importer.file_handlers.utility`

## Module Contents

`photogrammetry_importer.file_handlers.utility.check_radial_distortion(radial_distortion, camera_name, op=None)`

Check if the radial distortion is compatible with Blender.

`photogrammetry_importer.file_handlers.visualsfm_file_handler`

## Module Contents

`class photogrammetry_importer.file_handlers.visualsfm_file_handler.VisualSfMFileHandler`

Class to read and write VisualSfM files.

**classmethod** `parse_visualsfm_file(input_visual_fsm_file_name, image_dp, image_fp_type, suppress_distortion_warnings, op=None)`

Parse a VisualSfM (.nvm) file.

**classmethod** `write_visualsfm_file(output_nvm_file_name, cameras, points, op=None)`

Write cameras and points as .nvm file.

`photogrammetry_importer.importers`

Contains classes useful for import operators.

## Submodules

`photogrammetry_importer.importers.camera_animation_utility`

## Module Contents



```

photogrammetry_importer.importers.camera_animation_utility.add_camera_animation(cameras,
 par-
 ent_collection,
 anima-
 tion_frame_source='ORIGINAL',
 add_background_images=False,
 reorga-
 nize_undistorted_images=False,
 num-
 ber_interpolation_frames=0,
 interpola-
 tion_type='LINEAR',
 re-
 move_rotation_discontinuities=False,
 con-
 sider_missing_cameras_during_import=False,
 im-
 age_dp=None,
 im-
 age_fp_type=None,
 op=None)

```

Add an animated camera from a set of reconstructed cameras.

`photogrammetry_importer.importers.camera_importer`

## Module Contents

`class photogrammetry_importer.importers.camera_importer.CameraImporter`

Importer for cameras and corresponding image information.

`use_workspace_images : BoolProperty(name='Use Workspace Images', description='If selected, use the (undistorted) images in the workspace (if available). Otherwise use the images in the default image path.', default=True)`

`image_fp_items = [None, None, None]`

`image_fp_type : EnumProperty(name='Image File Path Type', description='Choose how image file paths are treated, i.e. absolute path, relative path or file name', items=image_fp_items)`

`image_dp : StringProperty(name='Image Directory', description='Assuming that the SfM reconstruction result is located in <some/path/rec.ext> or <some/path/rec_directory>. The addons uses either <some/path/images> (if available) or <some/path> as default image path. For MVS reconstruction results of Colmap, Meshroom or MVE the addon may or may not search for the images inside the corresponding workspace', default='')`

`import_cameras : BoolProperty(name='Import Cameras', description='Import Cameras', default=True)`

`default_width : IntProperty(name='Default Width', description='Width, which will be used if corresponding image is not found', default=-1)`

```
default_height :IntProperty(name='Default Height', description='Height, which will
be used if corresponding image is not found', default=-1)

default_focal_length :FloatProperty(name='Focal length in pixel', description='Value
for missing focal length in LOG (Open3D) file. ', default=float('nan'))

default_pp_x :FloatProperty(name='Principal Point X Component',
description='Principal Point X Component, which will be used if not contained in the
NVM (VisualSfM) / LOG (Open3D) file. If no value is provided, the principal point is
set to the image center', default=float('nan'))

default_pp_y :FloatProperty(name='Principal Point Y Component',
description='Principal Point Y Component, which will be used if not contained in the
NVM (VisualSfM) / LOG (Open3D) file. If no value is provided, the principal point is
set to the image center', default=float('nan'))

add_background_images :BoolProperty(name='Add a Background Image for each Camera',
description='The background image is only visible by viewing the scene from a
specific camera', default=True)

add_image_planes :BoolProperty(name='Add an Image Plane for each Camera',
description='Add an Image Plane for each Camera - only for non-panoramic cameras',
default=False)

add_image_plane_emission :BoolProperty(name='Add Image Plane Color Emission',
description='Add image plane color emission to increase the visibility of the image
planes', default=True)

image_plane_transparency :FloatProperty(name='Image Plane Transparency Value',
description='Transparency value of the image planes: 0 = invisible, 1 = opaque',
default=0.5, min=0, max=1)

add_depth_maps_as_point_cloud :BoolProperty(name='Add Depth Maps (EXPERIMENTAL)',
description='Add the depth map (if available) as point cloud for each Camera',
default=False)

use_default_depth_map_color :BoolProperty(name='Use Default Depth Map Color',
description='If not selected, each depth map is colorized with a different (random)
color', default=False)

depth_map_default_color :FloatVectorProperty(name='Depth Map Color',
description='Depth map color', subtype='COLOR', size=3, default=(0.0, 1.0, 0.0),
min=0.0, max=1.0)

depth_map_display_sparsity :IntProperty(name='Depth Map Display Sparsity',
description='Adjust the sparsity of the depth maps. A value of 10 means that every
10th depth map value is converted to a 3D point', default=10, min=1)

depth_map_id_or_name_str :StringProperty(name='Depth Map IDs or Names to Display',
description='A list of camera indices or names (separated by whitespaces) used to
select the depth maps, which will be displayed as point clouds. If no indices are
provided, all depth maps are shown. The names must not contain whitespaces',
default='')
```

```

add_camera_motion_as_animation :BoolProperty(name='Add Camera Motion as Animation',
description='Add an animation reflecting the camera motion. The order of the cameras
is determined by the corresponding file name', default=True)

animation_frame_source :EnumProperty(name='Use original frames', items=((('ORIGINAL',
'Original Frames', ''), ('ADJUSTED', 'Adjusted Frames', '')))

add_animated_camera_background_images :BoolProperty(name='Add Background Images for
the Animated Camera', description='The background images are only visible by viewing
the scene from the animated camera at the corresponding time step', default=True)

reorganize_undistorted_images :BoolProperty(name='Reorganize Undistorted Workspace
Images', description='Rename the undistorted images according to the original image
names and write them to a single directory. Certain libraries such as Meshroom or
MVE rename or move the undistorted images to different directories. Thus, the
reversal is necessary to use the images as background sequence for the animated
camera. WARNING: This will write a copy of the corresponding images to the workspace
directory', default=True)

number_interpolation_frames :IntProperty(name='Number of Frames Between two
Reconstructed Cameras', description='The poses of the animated camera are
interpolated', default=0, min=0)

interpolation_items = [['LINEAR', 'LINEAR', '', 1], ['BEZIER', 'BEZIER', '', 2],
['SINE', 'SINE', '', 3], ['QUAD',...

interpolation_type :EnumProperty(name='Interpolation Type', description='Blender
string that defines the type of the interpolation', items=interpolation_items)

consider_missing_cameras_during_animation :BoolProperty(name='Adjust Frame Numbers
of Camera Animation', description='Assume there are three consecutive images A,B and
C, but only A and C have been reconstructed. This option adjusts the frame number of
C and the number of interpolation frames between camera A and C', default=True)

remove_rotation_discontinuities :BoolProperty(name='Remove Rotation
Discontinuities', description='The addon uses quaternions q to represent the
rotation. A quaternion q and its negative -q describe the same rotation. This option
allows to remove different signs', default=True)

suppress_distortion_warnings :BoolProperty(name='Suppress Distortion Warnings',
description='Radial distortion might lead to incorrect alignments of cameras and
points. Enable this option to suppress corresponding warnings. If possible, consider
to re-compute the reconstruction using a camera model without radial distortion',
default=False)

adjust_render_settings :BoolProperty(name='Adjust Render Settings',
description='Adjust the render settings according to the corresponding images - all
images have to be captured with the same device. If disabled the visualization of
the camera cone in 3D view might be incorrect', default=True)

camera_extent :FloatProperty(name='Initial Camera Extent (in Blender Units)',
description='Initial Camera Extent (Visualization)', default=1)

draw_camera_options(layout, draw_workspace_image_usage=False,
 reorganize_undistorted_images=False, draw_image_fp=True,
 draw_depth_map_import=False, draw_image_size=False,
 draw_principal_point=False, draw_focal_length=False, draw_everything=False)

```

Draw camera import options.

**set\_intrinsics\_of\_cameras**(*cameras*)

Set intrinsic parameters of cameras.

This function should be overwritten, if the intrinsic parameters are not part of the reconstruction data (e.g. log file).

**set\_image\_size\_of\_cameras**(*cameras*)

Set image size of cameras.

This function should be overwritten, if the image size is not part of the reconstruction data (e.g. nvm file).

**import\_photogrammetry\_cameras**(*cameras*, *parent\_collection*)

Import the cameras using the properties of this class.

**photogrammetry\_importer.importers.camera\_utility**

## Module Contents

**photogrammetry\_importer.importers.camera\_utility.compute\_principal\_point\_shift**(*camera*, *relativ\_to\_largest\_extend*)

Return the shift of the principal point in the 3D view port.

**photogrammetry\_importer.importers.camera\_utility.adjust\_render\_settings\_if\_possible**(*cameras*, *op=None*)

Adjust the render settings according to the camera parameters.

**photogrammetry\_importer.importers.camera\_utility.add\_camera\_object**(*camera*, *camera\_name*, *camera\_collection*, *copy\_matrix\_world=True*)

Add a camera as Blender object.

**photogrammetry\_importer.importers.camera\_utility.invert\_y\_and\_z\_axis**(*input\_matrix\_or\_vector*)

Invert the y and z axis of a given matrix or vector.

Many SfM / MVS libraries use coordinate systems that differ from Blender's coordinate system in the y and the z coordinate. This function inverts the y and the z coordinates in the corresponding matrix / vector entries, which is equivalent to a rotation by 180 degree around the x axis.

**photogrammetry\_importer.importers.camera\_utility.compute\_camera\_matrix\_world**(*camera*, *convert\_coordinate\_system=True*)

Compute Blender's *matrix\_world* for a given camera.

```
photogrammetry_importer.importers.camera_utility.add_cameras(cameras, parent_collection,
 add_background_images=False,
 add_image_planes=False,
 add_depth_maps_as_point_cloud=True,
 con-
 vert_camera_coordinate_system=True,
 cam-
 era_collection_name='Cameras',
 im-
 age_plane_collection_name='Image
 Planes',
 depth_map_collection_name='Depth
 Maps', camera_scale=1.0,
 image_plane_transparency=0.5,
 add_image_plane_emission=True,
 depth_map_point_size=1,
 use_default_depth_map_color=False,
 depth_map_default_color=(1.0, 0.0,
 0.0),
 depth_map_display_sparsity=10,
 depth_map_id_or_name_str="",
 op=None)
```

Add a set of reconstructed cameras to Blender's 3D view port.

```
photogrammetry_importer.importers.camera_utility.add_camera_image_plane(matrix_world,
 blender_image,
 camera, name,
 transparency,
 add_image_plane_emission,
 im-
 age_planes_collection,
 op=None)
```

Add an image plane corresponding to a reconstructed camera.

**photogrammetry\_importer.importers.mesh\_importer**

## Module Contents

```
class photogrammetry_importer.importers.mesh_importer.MeshImporter
```

Importer for meshes.

```
import_mesh :BoolProperty(name='Import Mesh', description='Import mesh (if
available). Only relevant for files/folders referencing/containing mesh files (such
as *.mg files of Meshroom or dense Colmap folders). Note that Blenders build-in ply-
and obj-importer are quite slow', default=False)
```

```
add_mesh_color_emission :BoolProperty(name='Add Color Emission of Mesh',
description='Enabling color emission improves the visibility of the mesh colors',
default=True)
```

```
draw_mesh_options(layout)
```

Draw mesh import options.

```
import_photogrammetry_mesh(mesh_fp, reconstruction_collection)
```

Import a mesh using the properties of this class.

`photogrammetry_importer.importers.mesh_utility`

## Module Contents

```
photogrammetry_importer.importers.mesh_utility.add_color_emission_to_material(mesh_obj)
```

Add color emission for the given mesh to improve the visibility.

```
photogrammetry_importer.importers.mesh_utility.add_mesh_vertex_color_material(mesh_obj,
 mesh_material_name,
 add_mesh_color_emission)
```

Add a material with vertex colors to the given mesh.

`photogrammetry_importer.importers.point_importer`

## Module Contents

```
class photogrammetry_importer.importers.point_importer.PointImporter
```

Importer for points.

```
import_points : BoolProperty(name='Import Points', description='Import Points',
 default=True)
```

```
point_cloud_display_sparsity : IntProperty(name='Point Cloud Display Sparsity',
 description='Adjust the sparsity of the point cloud. A value of n means that every
n-th point in the point cloud is added', default=1, min=1)
```

```
center_points : BoolProperty(name='Center Data Around Origin', description='Center
data by subtracting the centroid. Useful for las/laz files, which contain usually
large offsets.', default=False)
```

```
draw_points_with_gpu : BoolProperty(name='Draw Points in the 3D View with OpenGL.',
 description='Draw Points in the 3D View. Allows to visualize point clouds with many
elements. These are not visible in eevee/cycles renderings.', default=True)
```

```
add_points_to_point_cloud_handle : BoolProperty(name='Add point data to the point
cloud handle.', description='This allows to draw the point cloud (again) with OpenGL
after saving and reloading the blend file.', default=True)
```

```
point_size : IntProperty(name='Initial Point Size', description='Initial Point Size',
 default=5)
```

```
add_points_as_mesh_object : BoolProperty(name='Add Points as Mesh Object',
 description='Use a mesh object to represent the point cloud with the vertex
positions.', default=False)
```

```
add_mesh_to_point_geometry_nodes : BoolProperty(name='Add Geometry Nodes',
 description='Add Geometry Nodes to allow rendering of the point cloud with Blender's
built-in renderers (Eevee / Cycles).', default=True)
```

```
point_radius :FloatProperty(name='Initial Point Radius', description='Initial point
radius (can be changed in GUI).', default=0.05)
```

```
point_subdivisions :IntProperty(name='Initial Point Subdivisions',
description='Initial point subdivisions (can be changed in GUI).', default=1)
```

```
add_color_as_custom_property :BoolProperty(name='Add Colors as Custom Property',
description='Use a custom property (named colors) to store the point cloud colors.',
default=True)
```

```
draw_point_options(layout, draw_everything=False)
```

Draw point import options.

```
import_photogrammetry_points(points, reconstruction_collection)
```

Import a point cloud using the properties of this class.

`photogrammetry_importer.importers.point_utility`

## Module Contents

```
photogrammetry_importer.importers.point_utility.add_points_as_object_with_particle_system(points,
re-
con-
struc-
tion_collection,
mesh_type='CUB',
point_extent=0.0,
add_particle_color=True,
par-
ti-
cle_overwrite_color=False,
op=None)
```

Add a point cloud as particle system.

This method is deprecated. It is recommended to use `add_points_as_mesh_vertices()` instead.

```
photogrammetry_importer.importers.point_utility.create_geometry_nodes_node_group()
```

Create a new node group for a geometry nodes modifier.

```
photogrammetry_importer.importers.point_utility.add_points_as_mesh_vertices(points,
reconstruc-
tion_collection,
add_mesh_to_point_geometry_node=True,
point_radius=0.05,
point_subdivisions=1,
add_color_as_custom_property=True,
op=None)
```

Add a point cloud as mesh.

## `photogrammetry_importer.opengl`

Contains OpenGL functions to render point clouds.

### Submodules

## `photogrammetry_importer.opengl.draw_manager`

### Module Contents

#### **class** `photogrammetry_importer.opengl.draw_manager.DrawManager`

Class that allows to represent point clouds with OpenGL in Blender.

##### **classmethod** `get_singleton()`

Return a singleton of this class.

##### **register\_points\_draw\_callback**(*object\_anchor, coords, colors, point\_size*)

Register a callback to draw a point cloud.

##### **get\_coords\_and\_colors**(*visible\_only=False*)

Return the coordinates and the colors of the maintained points.

##### **delete\_anchor**(*object\_anchor*)

Delete the anchor used to control the pose of the point cloud.

##### **get\_draw\_callback\_handler**(*object\_anchor*)

Get the draw callback handler corresponding to the object anchor.

## `photogrammetry_importer.opengl.utility`

### Module Contents

`photogrammetry_importer.opengl.utility.draw_points`(*points, point\_size, add\_points\_to\_point\_cloud\_handle, reconstruction\_collection=None, object\_anchor\_handle\_name='OpenGL Point Cloud', op=None*)

Draw points using OpenGL.

`photogrammetry_importer.opengl.utility.draw_coords`(*coords, color=(0, 0, 255, 1.0), point\_size=1, add\_points\_to\_point\_cloud\_handle=True, reconstruction\_collection=None, object\_anchor\_handle\_name='OpenGL Coord Point Cloud', op=None*)

Draw coordinates using OpenGL.

`photogrammetry_importer.opengl.utility.redraw_points`(*dummy*)

Redraw points of the previous Blender session.

`photogrammetry_importer.opengl.utility.render_opengl_image`(*image\_name, cam, coords, colors, point\_size*)

Render the given coordinates with OpenGL.



## photogrammetry\_importer.operators

Contains Operators to import and export different formats into Blender.

### Submodules

## photogrammetry\_importer.operators.colmap\_export\_op

### Module Contents

```
class photogrammetry_importer.operators.colmap_export_op.ExportColmapOperator
 Bases: photogrammetry_importer.operators.export_op.ExportOperator, bpy_extras.io_utils.ExportHelper
 Blender operator to export a Colmap model.
 bl_idname = export_scene.colmap
 bl_label = Export Colmap
 bl_options
 directory :StringProperty()
 files :CollectionProperty(name='Directory Path', description='Directory path used
 for exporting the Colmap model', type=bpy.types.OperatorFileListElement)
 filename_ext =
 execute(context)
 Export selected cameras and points as Colmap model.
```

## photogrammetry\_importer.operators.colmap\_import\_op

### Module Contents

```
class photogrammetry_importer.operators.colmap_import_op.ImportColmapOperator
 Bases:
 photogrammetry_importer.operators.import_op.ImportOperator,
 photogrammetry_importer.importers.camera_importer.CameraImporter,
 photogrammetry_importer.importers.point_importer.PointImporter,
 photogrammetry_importer.importers.mesh_importer.MeshImporter,
 photogrammetry_importer.operators.general_options.GeneralOptions
 Blender operator to import a Colmap model/workspace.
 bl_idname = import_scene.colmap_model
 bl_label = Import Colmap Model Folder
 bl_options
 directory :StringProperty()
```

**execute**(*context*)

Import a Colmap model/workspace.

**invoke**(*context*, *event*)

Set the default import options before running the operator.

**draw**(*context*)

Draw the import options corresponding to this operator.

**photogrammetry\_importer.operators.export\_op**

### Module Contents

**class** photogrammetry\_importer.operators.export\_op.**ExportOperator**

Bases: bpy.types.Operator

Abstract basic export operator.

**get\_selected\_cameras\_and\_vertices\_of\_meshes**(*odp*)

Get selected cameras and vertices.

**abstract execute**(*context*)

Abstract method that must be overridden by a subclass.

**photogrammetry\_importer.operators.general\_options**

### Module Contents

**class** photogrammetry\_importer.operators.general\_options.**GeneralOptions**

Class to define and apply general options.

**adjust\_clipping\_distance** :BoolProperty(name='Adjust Clipping Distance',  
description='Adjust clipping distance of 3D view.', default=False)

**draw\_general\_options**(*layout*)

Draw general options.

**apply\_general\_options**()

Apply the options defined by this class.

**photogrammetry\_importer.operators.import\_op**

### Module Contents

**class** photogrammetry\_importer.operators.import\_op.**ImportOperator**

Bases: bpy.types.Operator

Abstract basic import operator.

**initialize\_options\_from\_addon\_preferences**()

Initialize the import options from the current addon preferences.

**get\_default\_image\_path**(*reconstruction\_fp, image\_dp*)  
Get the (default) path that defines where to look for images.

**abstract execute**(*context*)  
Abstract method that must be overridden by a subclass.

`photogrammetry_importer.operators.meshroom_import_op`

## Module Contents

```
class photogrammetry_importer.operators.meshroom_import_op.ImportMeshroomOperator
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
 photogrammetry_importer.importers.camera_importer.CameraImporter,
 photogrammetry_importer.importers.point_importer.PointImporter,
 photogrammetry_importer.importers.mesh_importer.MeshImporter,
 photogrammetry_importer.operators.general_options.GeneralOptions, bpy_extras.
 io_utils.ImportHelper
 Import a Meshroom MG/SfM/JSON file.
 bl_idname = import_scene.meshroom_sfm_json
 bl_label = Import Meshroom SfM/JSON/MG
 bl_options

 filepath :StringProperty(name='Meshroom JSON File Path', description='File path used
 for importing the Meshroom SfM/JSON/MG' + ' file')

 directory :StringProperty()

 filter_glob :StringProperty(default='*.sfm;*.json;*.mg', options={'HIDDEN'})

 sfm_node_items = [['AUTOMATIC', 'AUTOMATIC', '', 1], ['ConvertSfMFormatNode',
 'ConvertSfMFormatNode', '', 2],...]

 sfm_node_type :EnumProperty(name='Structure From Motion Node Type', description='Use
 this property to select the node with the structure' + ' from motion results to
 import', items=sfm_node_items)

 sfm_node_number :IntProperty(name='ConvertSfMFormat Node Number', description='Use
 this property to select the desired node.' + ' By default the node with the highest
 number is imported.', default=-1)

 mesh_node_items = [['AUTOMATIC', 'AUTOMATIC', '', 1], ['Texturing', 'Texturing', '',
 2], ['MeshFiltering',...]

 mesh_node_type :EnumProperty(name='Mesh Node Type', description='Use this property
 to select the node with the mesh' + ' results to import', items=mesh_node_items)

 mesh_node_number :IntProperty(name='Mesh Node Number', description='Use this
 property to select the desired node.' + ' By default the node with the highest
 number is imported.', default=-1)
```

```
prepare_node_number :IntProperty(name='Prepare Dense Node Number', description='Use
this property to select the desired node.' + ' By default the node with the highest
number is imported.', default=-1)
```

```
execute(context)
```

```
 Import a Meshroom file/workspace.
```

```
invoke(context, event)
```

```
 Set the default import options before running the operator.
```

```
draw(context)
```

```
 Draw the import options corresponding to this operator.
```

`photogrammetry_importer.operators.mve_import_op`

## Module Contents

```
class photogrammetry_importer.operators.mve_import_op.ImportMVEOperator
```

```
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
photogrammetry_importer.importers.camera_importer.CameraImporter,
photogrammetry_importer.importers.point_importer.PointImporter,
photogrammetry_importer.operators.general_options.GeneralOptions
```

```
 Import a Multi-View Environment reconstruction folder.
```

```
bl_idname = import_scene.mve_folder
```

```
bl_label = Import MVE Folder
```

```
bl_options
```

```
directory :StringProperty()
```

```
execute(context)
```

```
 Import an MVE workspace.
```

```
invoke(context, event)
```

```
 Set the default import options before running the operator.
```

```
draw(context)
```

```
 Draw the import options corresponding to this operator.
```

`photogrammetry_importer.operators.open3d_import_op`

## Module Contents

```
class photogrammetry_importer.operators.open3d_import_op.ImportOpen3DOperator
```

```
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
photogrammetry_importer.importers.camera_importer.CameraImporter,
photogrammetry_importer.importers.point_importer.PointImporter,
photogrammetry_importer.operators.general_options.GeneralOptions, bpy_extras.
io_utils.ImportHelper
```

```
 Import an Open3D LOG/JSON file
```

```

bl_idname = import_scene.open3d_log_json

bl_label = Import Open3D LOG/JSON

bl_options

filepath :StringProperty(name='Open3D LOG/JSON File Path', description='File path
used for importing the Open3D LOG/JSON file')

directory :StringProperty()

filter_glob :StringProperty(default='*.log;*.json', options={'HIDDEN'})

set_intrinsics_of_cameras(cameras)
 Enhances the imported cameras with intrinsic information.
 Overwrites the method in CameraImporter.

set_image_size_of_cameras(cameras)
 Enhance the imported cameras with image related information.
 Overwrites the method in CameraImporter.

execute(context)
 Import an Open3D file.

invoke(context, event)
 Set the default import options before running the operator.

draw(context)
 Draw the import options corresponding to this operator.

```

`photogrammetry_importer.operators.openmvg_import_op`

## Module Contents

```

class photogrammetry_importer.operators.openmvg_import_op.ImportOpenMVGOperator
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
photogrammetry_importer.importers.camera_importer.CameraImporter,
photogrammetry_importer.importers.point_importer.PointImporter,
photogrammetry_importer.operators.general_options.GeneralOptions, bpy_extras.
io_utils.ImportHelper
 Import an OpenMVG JSON file
 bl_idname = import_scene.openmvg_json
 bl_label = Import OpenMVG JSON
 bl_options

 filepath :StringProperty(name='OpenMVG JSON File Path', description='File path used
 for importing the OpenMVG JSON file')

 directory :StringProperty()

 filter_glob :StringProperty(default='*.json', options={'HIDDEN'})

```

**execute**(*context*)

Import an OpenMVG JSON file.

**invoke**(*context*, *event*)

Set the default import options before running the operator.

**draw**(*context*)

Draw the import options corresponding to this operator.

`photogrammetry_importer.operators.opensfm_import_op`

## Module Contents

**class** `photogrammetry_importer.operators.opensfm_import_op.ImportOpenSfmOperator`

Bases: `photogrammetry_importer.operators.import_op.ImportOperator`,  
`photogrammetry_importer.importers.camera_importer.CameraImporter`,  
`photogrammetry_importer.importers.point_importer.PointImporter`,  
`photogrammetry_importer.operators.general_options.GeneralOptions`, `bpy_extras.io_utils.ImportHelper`

Import an OpenSfM JSON file

**bl\_idname** = `import_scene.opensfm_json`

**bl\_label** = `Import OpenSfM JSON`

**bl\_options**

**filepath** :`StringProperty`(name='OpenSfM JSON File Path', description='File path used for importing the OpenSfM JSON file')

**directory** :`StringProperty`()

**filter\_glob** :`StringProperty`(default='\*.json', options={'HIDDEN'})

**reconstruction\_number** :`IntProperty`(name='Reconstruction Number', description='If the input file contains multiple reconstructions, use' + ' this property to select the desired reconstruction.', default=0)

**execute**(*context*)

Import an OpenSfM JSON file.

**invoke**(*context*, *event*)

Set the default import options before running the operator.

**draw**(*context*)

Draw the import options corresponding to this operator.

`photogrammetry_importer.operators.point_data_import_op`

## Module Contents

```
class photogrammetry_importer.operators.point_data_import_op.ImportPointDataOperator
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
 photogrammetry_importer.importers.point_importer.PointImporter,
 photogrammetry_importer.operators.general_options.GeneralOptions, bpy_extras.
 io_utils.ImportHelper

 Import point data (e.g. a PLY file) as point cloud.

 bl_idname = import_scene.point_data

 bl_label = Import Point Data

 bl_options

 filepath :StringProperty(name='Point Data File Path', description='File path used
 for importing the point data file')

 directory :StringProperty()

 filter_glob :StringProperty(default='*.ply;*.pcd;*.las;*.laz;*.asc;*.pts;*.csv',
 options={'HIDDEN'})

 execute(context)
 Import a file with point data (e.g. PLY).

 invoke(context, event)
 Set the default import options before running the operator.

 draw(context)
 Draw the import options corresponding to this operator.
```

`photogrammetry_importer.operators.utility`

## Module Contents

```
photogrammetry_importer.operators.utility.set_image_size_for_cameras(cameras, default_width,
 default_height, op=None)

 Set image sizes for cameras and return a boolean.
```

`photogrammetry_importer.operators.visualsfm_export_op`

## Module Contents

```
class photogrammetry_importer.operators.visualsfm_export_op.ExportVisualSfMOperator
 Bases: photogrammetry_importer.operators.export_op.ExportOperator, bpy_extras.io_utils.
 ExportHelper

 Export a VisualSfM file.
```

```
bl_idname = export_scene.nvm

bl_label = Export NVM

bl_options

directory :StringProperty()

files :CollectionProperty(name='File Path', description='File path used for
exporting the NVM file', type=bpy.types.OperatorFileListElement)

filename_ext = .nvm

filter_glob :StringProperty(default='*.nvm', options={'HIDDEN'})

execute(context)
 Export selected cameras and points as VisualSfM file.
```

`photogrammetry_importer.operators.visualsfm_import_op`

## Module Contents

```
class photogrammetry_importer.operators.visualsfm_import_op.ImportVisualSfMOperator
 Bases: photogrammetry_importer.operators.import_op.ImportOperator,
photogrammetry_importer.importers.camera_importer.CameraImporter,
photogrammetry_importer.importers.point_importer.PointImporter,
photogrammetry_importer.operators.general_options.GeneralOptions, bpy_extras.
io_utils.ImportHelper
 Import a VisualSfM NVM file.
 bl_idname = import_scene.visualsfm_nvm
 bl_label = Import NVM
 bl_options

 filepath :StringProperty(name='NVM File Path', description='File path used for
importing the NVM file')

 directory :StringProperty()

 filter_glob :StringProperty(default='*.nvm', options={'HIDDEN'})

 set_image_size_of_cameras(cameras)
 Enhance the imported cameras with image related information.
 Overwrites the method in CameraImporter.

 execute(context)
 Import an VisualSfM file.

 invoke(context, event)
 Set the default import options before running the operator.

 draw(context)
 Draw the import options corresponding to this operator.
```



## `photogrammetry_importer.panels`

Contains GUI elements to adjust and leverage the imported objects.

### Submodules

## `photogrammetry_importer.panels.render_operators`

### Module Contents

```
class photogrammetry_importer.panels.render_operators.SaveOpenGLRenderImageOperator
```

Bases: `bpy.types.Operator`

An Operator to save a rendering of the point cloud as Blender image.

```
bl_idname = photogrammetry_importer.save_opengl_render_image
```

```
bl_label = Save as Blender Image
```

```
bl_description = Use a single camera to render the point cloud.
```

```
classmethod poll(context)
```

Return the availability status of the operator.

```
execute(context)
```

Render the point cloud and save the result as image in Blender.

```
class photogrammetry_importer.panels.render_operators.ExportOpenGLRenderImageOperator
```

Bases: `bpy.types.Operator`, `bpy_extras.io_utils.ExportHelper`

An Operator to save a rendering of the point cloud to disk.

```
bl_idname = photogrammetry_importer.export_opengl_render_image
```

```
bl_label = Export Point Cloud Rendering as Image
```

```
bl_description = Use a single camera to render the point cloud.
```

```
filename_ext =
```

```
classmethod poll(context)
```

Return the availability status of the operator.

```
execute(context)
```

Render the point cloud and export the result as image.

```
class photogrammetry_importer.panels.render_operators.ExportOpenGLRenderAnimationOperator
```

Bases: `bpy.types.Operator`, `bpy_extras.io_utils.ExportHelper`

An Operator to save multiple renderings of the point cloud to disk.

```
bl_idname = photogrammetry_importer.export_opengl_render_animation
```

```
bl_label = Export Point Cloud Renderings as Image Sequence
```

```
bl_description = Use an animated camera to render the point cloud.
```

**filename\_ext** =

**classmethod poll**(*context*)

Return the availability status of the operator.

**execute**(*context*)

Render the point cloud and export the result as image sequence.

**photogrammetry\_importer.panels.screenshot\_operators**

## Module Contents

**class photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImageOperator**

Bases: bpy.types.Operator, bpy\_extras.io\_utils.ExportHelper

An Operator to export a screenshot (of the 3D view).

**bl\_idname** = photogrammetry\_importer.export\_screenshot

**bl\_label** = Export Screenshot

**bl\_description** = Create a screenshot (using a camera perspective).

**filename\_ext** =

**classmethod poll**(*context*)

Return the availability status of the operator.

**execute**(*context*)

Export a screenshot (of the 3D view).

**class**

**photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotAnimationOperator**

Bases: bpy.types.Operator, bpy\_extras.io\_utils.ExportHelper

An Operator to export a screenshot sequence (of the 3D view).

**bl\_idname** = photogrammetry\_importer.export\_screenshot\_sequence

**bl\_label** = Export Screenshot Sequence

**bl\_description** = Use the animation data to create a screenshot sequence.

**filename\_ext** =

**classmethod poll**(*context*)

Return the availability status of the operator.

**execute**(*context*)

Export a sequence of screenshots using the selected camera.

photogrammetry\_importer.panels.view\_3d\_panel

## Module Contents

**class** photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings

Bases: bpy.types.PropertyGroup

Class that defines the properties of the OpenGL panel in the 3D view.

**viz\_point\_size** :IntProperty(name='Point Size', description='OpenGL visualization point size.', get=get\_viz\_point\_size, set=set\_viz\_point\_size, min=1)

**only\_3d\_view** :BoolProperty(name='Export Only 3D View', description='Export only the 3D view or the full UI of Blender', default=True)

**use\_camera\_perspective** :BoolProperty(name='Use Perspective of Selected Camera', description='', default=True)

**screenshot\_file\_format** :StringProperty(name='File format', description='File format of the exported screenshot(s)', default='png')

**use\_camera\_keyframes\_for\_screenshots** :BoolProperty(name='Use Keyframes of Selected Camera', description='Use the Camera Keyframes instead of Animation Frames', default=True)

**save\_point\_size** :IntProperty(name='Point Size', description='OpenGL point size.', default=10)

**render\_file\_format** :StringProperty(name='File format', description='File format of the exported rendering(s)', default='png')

**save\_alpha** :BoolProperty(name='Save Alpha Values', description='Save alpha values (if possible) to disk.', default=True)

**use\_camera\_keyframes\_for\_rendering** :BoolProperty(name='Use Camera Keyframes', description='Use the Camera Keyframes instead of Animation Frames.', default=True)

**get\_viz\_point\_size()**

**set\_viz\_point\_size(value)**

**class** photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel

Bases: bpy.types.Panel

Class that defines the OpenGL panel in the 3D view.

**bl\_label** = OpenGL Panel

**bl\_idname** = EXPORT\_OPENGL\_PT\_render\_point\_cloud

**bl\_space\_type** = VIEW\_3D

**bl\_region\_type** = UI

**bl\_category** = PhotogrammetryImporter

**classmethod** poll(context)

Return the availability status of the panel.

**classmethod register()**

Register properties and operators corresponding to this panel.

**classmethod unregister()**

Unregister properties and operators corresponding to this panel.

**draw(context)**

Draw the panel with corresponding properties and operators.

## **photogrammetry\_importer.preferences**

Contains persistent addon preferences.

## **Submodules**

### **photogrammetry\_importer.preferences.addon\_preferences**

## **Module Contents**

**class photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences**

Bases: `bpy.types.AddonPreferences`, `photogrammetry_importer.importers.camera_importer.CameraImporter`, `photogrammetry_importer.importers.point_importer.PointImporter`, `photogrammetry_importer.importers.mesh_importer.MeshImporter`

Class to manage persistent addon preferences.

**bl\_idname**

**visible\_preferences** :EnumProperty(name='Use original frames', items=((('DEPENDENCIES', 'Dependencies', ''), ('IMPORTEREXPORTER', 'Importer / Exporter', '')), ('IMPORTOPTIONS', 'Import Options', '')))

**colmap\_importer\_bool** :BoolProperty(name='Colmap Importer', default=True)

**meshroom\_importer\_bool** :BoolProperty(name='Meshroom Importer', default=True)

**mve\_importer\_bool** :BoolProperty(name='MVE Importer', default=True)

**open3d\_importer\_bool** :BoolProperty(name='Open3D Importer', default=True)

**opensfm\_importer\_bool** :BoolProperty(name='OpenSfM Importer', default=True)

**openmvg\_importer\_bool** :BoolProperty(name='OpenMVG Importer', default=True)

**point\_data\_importer\_bool** :BoolProperty(name='Point Data Importer', default=True)

**visualsfm\_importer\_bool** :BoolProperty(name='VisualSfM Importer', default=True)

**colmap\_exporter\_bool** :BoolProperty(name='Colmap Exporter', default=True)

**visualsfm\_exporter\_bool** :BoolProperty(name='VisualSfM Exporter', default=True)

**sys\_path\_list\_str** :StringProperty(name='System Path List Decoded String', default='[]')

**classmethod register()**

Register corresponding operators.

**classmethod unregister()**

Unregister corresponding operators.

**draw(context)**

Draw available preference options.

**reset\_import\_options()**

Reset the import options to factor settings.

**class**

**photogrammetry\_importer.preferences.addon\_preferences.UpdateImporterExporterOperator**

Bases: bpy.types.Operator

Operator to activate and deactivate importers and exporters.

**bl\_idname = photogrammetry\_importer.update\_importer\_exporter**

**bl\_label = Update (Enable / Disable) Importers and Exporters**

**execute(context)**

Activate and deactivate importers and exporters.

Uses the selected options of [AddonPreferences](#) to determine active and inactive importers and exporters.

**class photogrammetry\_importer.preferences.addon\_preferences.ResetImportOptionsOperator**

Bases: bpy.types.Operator

Operator to reset import options.

**bl\_idname = photogrammetry\_importer.reset\_import\_options**

**bl\_label = Reset Import Options to Factory Settings**

**execute(context)**

Reset import options to factory settings.

**photogrammetry\_importer.preferences.dependency**

## Module Contents

**photogrammetry\_importer.preferences.dependency.get\_additional\_command\_line\_sys\_path()**

Function that retrieves additional sys.path of the command line

**photogrammetry\_importer.preferences.dependency.add\_command\_line\_sys\_path()**

Function that adds sys.path of the command line to Blender's sys.path

**photogrammetry\_importer.preferences.dependency.remove\_command\_line\_sys\_path()**

Function that removes additional paths in Blender's sys.path

**photogrammetry\_importer.preferences.dependency.add\_command\_line\_sys\_path\_if\_necessary(dummy)**

Function that extends Blender's sys.path if necessary

```
class photogrammetry_importer.preferences.dependency.DependencyStatus(gui_name,
 package_name,
 import_name)

 Class that describes the installation status of a Python dependency.

 get_package_info()

class photogrammetry_importer.preferences.dependency.PipManager
 Class that manages the pip installation.

 classmethod get_singleton()
 Return a singleton of this class.

 install_pip(lazy, op=None)
 Install pip.

 get_package_info()
 Return the pip installation status.

class photogrammetry_importer.preferences.dependency.OptionalDependency(gui_name,
 package_name,
 import_name)

 Bases: DependencyStatus

 Class that describes an optional Python dependency of the addon.

 install(op=None)
 Install this dependency.

 uninstall(remove_sys_path=True, op=None)
 Uninstall this dependency.

class photogrammetry_importer.preferences.dependency.OptionalDependencyManager
 Class that manages the (optional) dependencies of this addon.

 classmethod get_singleton()
 Return a singleton of this class.

 install_dependencies(dependency_package_name="", op=None)
 Install all (optional) dependencies of this addon.

 uninstall_dependencies(dependency_package_name="", op=None)
 Uninstall all (optional) dependencies of this addon.

 get_dependencies()
 Return all (optional) dependencies of this addon.

class photogrammetry_importer.preferences.dependency.InstallOptionalDependenciesOperator
 Bases: bpy.types.Operator

 Operator to install all (optional) dependencies of this addon.

 bl_idname = photogrammetry_importer.install_dependencies

 bl_label = Download and Install ALL Optional Dependencies (be patient!)

 bl_description = Download and install the optional dependencies (Python packages).
 Depending on the installation...
```

**bl\_options**

**dependency\_package\_name** :StringProperty(name='Dependency Package Name',  
description='Target dependency package to be installed.', default='')

**execute**(*context*)

Install all optional dependencies.

**class**

photogrammetry\_importer.preferences.dependency.UninstallOptionalDependenciesOperator

Bases: bpy.types.Operator

Operator to uninstall all (optional) dependencies of this addon.

**bl\_idname** = photogrammetry\_importer.uninstall\_dependencies

**bl\_label** = Remove ALL Optional Dependencies

**bl\_description** = Uninstall optional dependencies. Blender may have to be started  
with administrator privileges in...

**bl\_options**

**dependency\_package\_name** :StringProperty(name='Dependency Package Name',  
description='Target dependency package to be removed.', default='')

**execute**(*context*)

Uninstall all optional dependencies.

**photogrammetry\_importer.registration**

Contains functions to register import and export operators.

**Submodules****photogrammetry\_importer.registration.registration****Module Contents**

**class** photogrammetry\_importer.registration.registration.Registration

Class to register import and export operators.

**classmethod** register\_importers(*import\_prefs*)

Register importers according to the import preferences.

**classmethod** unregister\_importers()

Unregister all registered importers.

**classmethod** register\_exporters(*export\_prefs*)

Register exporters according to the export preferences.

**classmethod** unregister\_exporters()

Unregister all registered exporters.

## `photogrammetry_importer.types`

Contains data types used to represent reconstruction results.

## Submodules

### `photogrammetry_importer.types.camera`

## Module Contents

### `class photogrammetry_importer.types.camera.Camera`

This class represents a reconstructed camera.

It provides functionality to manage intrinsic and extrinsic camera parameters as well as corresponding image and depth map information.

`panoramic_type_equirectangular = EQUIRECTANGULAR`

`IMAGE_FP_TYPE_NAME = NAME`

`IMAGE_FP_TYPE_RELATIVE = RELATIVE`

`IMAGE_FP_TYPE_ABSOLUTE = ABSOLUTE`

`DEPTH_MAP_WRT_UNIT_VECTORS = DEPTH_MAP_WRT_UNIT_VECTORS`

`DEPTH_MAP_WRT_CANONICAL_VECTORS = DEPTH_MAP_WRT_CANONICAL_VECTORS`

`get_file_name()`

Return the file name of the image used to register this camera.

`set_relative_fp(relative_fp, image_fp_type)`

Set the relative file path of the corresponding image.

`get_relative_fp()`

Return the relative file path of the corresponding image.

`get_undistorted_relative_fp()`

Return the relative file path of the undistorted image.

`set_absolute_fp(absolute_fp)`

Set the absolute file path of the corresponding image.

`get_absolute_fp()`

Return the absolute file path of the corresponding image.

`get_undistorted_absolute_fp()`

Return the absolute file path of the undistorted image.

`has_undistorted_absolute_fp()`

Determine if there is an absolute path to the undistorted image.

`get_undistorted_file_name()`

Return the file name of the undistorted image.



**set\_calibration**(*calibration\_mat*, *radial\_distortion*)  
Set calibration matrix and distortion parameter.

**has\_focal\_length**()  
Return whether the focal length value has been defined or not.

**get\_focal\_length**()  
Return the focal length value.

**get\_field\_of\_view**()  
Return the field of view corresponding to the focal length.

**has\_intrinsics**()  
Return whether the intrinsic parameters have been defined or not.

**get\_calibration\_mat**()  
Return the calibration matrix.

**set\_calibration\_mat**(*calibration\_mat*)  
Set the calibration matrix.

**set\_principal\_point**(*principal\_point*)  
Set the principal point.

**get\_principal\_point**()  
Return the principal point.

**has\_principal\_point**()  
Return whether the principal point has been defined or not.

**is\_panoramic**()  
Return whether the camera model is a panoramic camera or not.

**set\_panoramic\_type**(*panoramic\_type*)  
Set the panoramic camera type.

**get\_panoramic\_type**()  
Return the panoramic camera type (if any).

**static compute\_calibration\_mat**(*focal\_length*, *cx*, *cy*)  
Return the calibration matrix.

**set\_rotation\_with\_quaternion**(*quaternion*)  
Set the camera rotation using a quaternion.

**set\_rotation\_with\_rotation\_mat**(*rotation\_mat*, *check\_rotation=True*)  
Set the camera rotation using a rotation matrix.

**set\_camera\_center\_after\_rotation**(*center*, *check\_rotation=True*)  
Set the camera center after setting the camera rotation.

**set\_camera\_translation\_vector\_after\_rotation**(*translation\_vector*, *check\_rotation=True*)  
Set the camera translation after setting the camera rotation.

**get\_rotation\_as\_quaternion**()  
Return the rotation as quaternion.

**get\_rotation\_as\_rotation\_mat**()  
Return the rotation as rotation matrix.

**get\_translation\_vec()**

Return the translation vector.

**get\_camera\_center()**

Return the camera center.

**set\_4x4\_cam\_to\_world\_mat**(*cam\_to\_world\_mat*, *check\_rotation=True*)

Set the extrinsic parameters.

**static quaternion\_to\_rotation\_matrix**(*q*)

Convert a quaternion to a rotation matrix.

**static rotation\_matrix\_to\_quaternion**(*m*)

Convert a rotation matrix to a quaternion.

**set\_depth\_map\_callback**(*depth\_map\_callback*, *depth\_map\_ifp*, *depth\_map\_semantic*,  
*shift\_depth\_map\_to\_pixel\_center*)

Set the depth map callback.

**get\_depth\_map\_fp()**

Return the depth map file path.

**get\_depth\_map()**

Return the depth map.

**get\_4x4\_cam\_to\_world\_mat()**

Return the camera to world transformation matrix.

This matrix can be used to convert homogeneous points given in camera coordinates to homogeneous points given in world coordinates.

**convert\_depth\_map\_to\_world\_coords**(*depth\_map\_display\_sparsity=100*)

Convert the depth map to points in world coordinates.

**convert\_cam\_coords\_to\_world\_coords**(*cam\_coords*)

Convert camera coordinates to world coordinates.

**convert\_depth\_map\_to\_cam\_coords**(*depth\_map\_display\_sparsity=100*)

Convert the depth map to points in camera coordinates.

**photogrammetry\_importer.types.point**

## Module Contents

**class photogrammetry\_importer.types.point.Point**

Bases: `namedtuple('Point', ['coord', 'color', 'id', 'scalars'])`

This class represents a three-dimensional point.

A point contains the following attributes: 3D coordinate, color, point id and a list of scalars.

**static split\_points**(*points*, *normalize\_colors=False*)

Split points into coordinates and colors.

**static create\_points**(*coords*, *colors*, *unnormailze\_colors=False*)

**static get\_centered\_points**(*points*)

## photogrammetry\_importer.utility

Contains general utility functions.

### Submodules

## photogrammetry\_importer.utility.developer\_utility

### Module Contents

`photogrammetry_importer.utility.developer_utility.setup_addon_modules`(*path*, *package\_name*, *reload*)

Imports and reloads all modules in this addon.

Individual modules can define a `__reload_order_index__` property which will be used to reload the modules in a specific order. The default is 0.

## photogrammetry\_importer.utility.os\_utility

### Module Contents

`photogrammetry_importer.utility.os_utility.get_file_paths_in_dir`(*idp*, *ext=None*,  
*target\_str\_or\_list=None*,  
*ignore\_str\_or\_list=None*,  
*base\_name\_only=False*,  
*relative\_path\_only=False*,  
*without\_ext=False*,  
*sort\_result=True*,  
*natural\_sorting=False*,  
*recursive=False*)

Return the paths of the files in the given directory.

The parameter `ext` can be a list of extensions or a single extension (e.g. `[.jpg, .png]` or `.jpg`).

`photogrammetry_importer.utility.os_utility.get_image_file_paths_in_dir`(*idp*,  
*base\_name\_only=False*,  
*relative\_path\_only=False*,  
*without\_ext=False*,  
*sort\_result=True*,  
*recursive=True*, *target\_str\_or\_list=None*)

Return the paths of the images in the given directory.

`photogrammetry_importer.utility.os_utility.get_subdirs`(*idp*, *base\_name\_only=False*,  
*sort\_result=True*, *natural\_sorting=False*,  
*recursive=False*)

Return the paths of the subdirectories in the given directory.

### photogrammetry\_importer.utility.timing\_utility

#### Module Contents

**class** photogrammetry\_importer.utility.timing\_utility.StopWatch

Bases: object

Class to measure computation times.

**reset\_time()**

Reset the stop watch to the current point in time.

**get\_elapsed\_time()**

Return the elapsed time.

### photogrammetry\_importer.utility.type\_utility

#### Module Contents

photogrammetry\_importer.utility.type\_utility.is\_int(*some\_str*)

Return True, if the given string represents an integer value.

photogrammetry\_importer.utility.type\_utility.is\_float(*some\_str*)

Return True, if the given string represents a float value.

### photogrammetry\_importer.utility.ui\_utility

#### Module Contents

photogrammetry\_importer.utility.ui\_utility.add\_multi\_line\_label(*ui\_layout*, *long\_text*,  
*max\_line\_length=120*)

#### Package Contents

photogrammetry\_importer.bl\_info

photogrammetry\_importer.modules

photogrammetry\_importer.register()

Register importers, exporters and panels.

photogrammetry\_importer.unregister()


Unregister importers, exporters and panels.

There is a short [tutorial video](#) that shows how to

- install the addon
- compute a reconstruction with Meshroom
- import the results into Blender

### EXAMPLE RESULTS (SHIPPED WITH ADDON)

This repository contains an example Colmap model. The following image shows the imported camera poses, image planes and point cloud in Blender's 3D view.




The input images of the Colmap model are located here: [https://github.com/openMVG/ImageDataset\\_SceauxCastle](https://github.com/openMVG/ImageDataset_SceauxCastle).


The addon computes an animated camera with corresponding background images from the reconstructed camera poses.

There is also an import option that allows to interpolate the reconstructed camera poses.

In addition, the addon allows to import meshes contained in the workspaces of specific libraries. Manually imported meshes can also be aligned with the corresponding reconstruction by following the instructions [here](#).



The addon offers an option to draw big point clouds with OpenGL to reduce computational requirements. The addon provides a panel to export these OpenGL point clouds renderings - see [Point Cloud Visualization and Rendering](#).





## PYTHON MODULE INDEX

**p** 41  
 photogrammetry\_importer, 31 photogrammetry\_importer.importers.mesh\_utility, 42  
 photogrammetry\_importer.blender\_utility, 31 photogrammetry\_importer.importers.point\_importer, 42  
 photogrammetry\_importer.blender\_utility.image\_utility, 42  
 photogrammetry\_importer.blender\_utility.logging\_utility, 43  
 photogrammetry\_importer.blender\_utility.object\_utility, 44  
 photogrammetry\_importer.blender\_utility.opengl, 44  
 photogrammetry\_importer.blender\_utility.opengl.draw\_manager, 44  
 photogrammetry\_importer.blender\_utility.retrieval\_utility, 44  
 photogrammetry\_importer.blender\_utility.opengl.utility, 44  
 photogrammetry\_importer.file\_handlers, 33 photogrammetry\_importer.operators, 45  
 photogrammetry\_importer.file\_handlers.colmap\_file\_handler, 45  
 photogrammetry\_importer.file\_handlers.colmap\_export\_op, 45  
 photogrammetry\_importer.file\_handlers.colmap\_import\_op, 45  
 photogrammetry\_importer.file\_handlers.meshroom\_file\_handler, 46  
 photogrammetry\_importer.file\_handlers.meshroom\_import\_op, 46  
 photogrammetry\_importer.file\_handlers.mve\_file\_handler, 46  
 photogrammetry\_importer.file\_handlers.mve\_import\_op, 46  
 photogrammetry\_importer.file\_handlers.open3D\_file\_handler, 46  
 photogrammetry\_importer.file\_handlers.open3d\_import\_op, 46  
 photogrammetry\_importer.file\_handlers.openmvg\_file\_handler, 47  
 photogrammetry\_importer.file\_handlers.openmvg\_import\_op, 47  
 photogrammetry\_importer.file\_handlers.opensfm\_file\_handler, 48  
 photogrammetry\_importer.file\_handlers.opensfm\_import\_op, 48  
 photogrammetry\_importer.file\_handlers.point\_data\_file\_handler, 48  
 photogrammetry\_importer.file\_handlers.point\_data\_import\_op, 48  
 photogrammetry\_importer.file\_handlers.transformation\_file\_handler, 49  
 photogrammetry\_importer.file\_handlers.transformation\_import\_op, 49  
 photogrammetry\_importer.file\_handlers.utility, 50  
 photogrammetry\_importer.file\_handlers.utility\_import\_op, 50  
 photogrammetry\_importer.file\_handlers.visualsfm\_file\_handler, 51  
 photogrammetry\_importer.file\_handlers.visualsfm\_import\_op, 51  
 photogrammetry\_importer.importers, 36 photogrammetry\_importer.operators.utility, 51  
 photogrammetry\_importer.importers.camera\_animation\_utility, 51  
 photogrammetry\_importer.importers.camera\_importer, 52  
 photogrammetry\_importer.importers.camera\_import\_op, 52  
 photogrammetry\_importer.importers.camera\_utility, 53  
 photogrammetry\_importer.importers.camera\_utility\_import\_op, 53  
 photogrammetry\_importer.importers.mesh\_importer, 53

photogrammetry\_importer.panels.screenshot\_operators,  
54  
photogrammetry\_importer.panels.view\_3d\_panel,  
55  
photogrammetry\_importer.preferences, 56  
photogrammetry\_importer.preferences.addon\_preferences,  
56  
photogrammetry\_importer.preferences.dependency,  
57  
photogrammetry\_importer.registration, 59  
photogrammetry\_importer.registration.registration,  
59  
photogrammetry\_importer.types, 60  
photogrammetry\_importer.types.camera, 60  
photogrammetry\_importer.types.point, 62  
photogrammetry\_importer.utility, 63  
photogrammetry\_importer.utility.developer\_utility,  
63  
photogrammetry\_importer.utility.os\_utility,  
63  
photogrammetry\_importer.utility.timing\_utility,  
64  
photogrammetry\_importer.utility.type\_utility,  
64  
photogrammetry\_importer.utility.ui\_utility,  
64



## INDEX

### A

- add\_animated\_camera\_background\_images  
(photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39
- add\_background\_images (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38
- add\_camera\_animation() (in module photogrammetry\_importer.importers.camera\_animation\_utility), 36
- add\_camera\_image\_plane() (in module photogrammetry\_importer.importers.camera\_utility), 41
- add\_camera\_motion\_as\_animation (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38
- add\_camera\_object() (in module photogrammetry\_importer.importers.camera\_utility), 40
- add\_cameras() (in module photogrammetry\_importer.importers.camera\_utility), 40
- add\_collection() (in module photogrammetry\_importer.blender\_utility.object\_utility), 32
- add\_color\_as\_custom\_property (photogrammetry\_importer.importers.point\_importer.PointImporter attribute), 43
- add\_color\_emission\_to\_material() (in module photogrammetry\_importer.importers.mesh\_utility), 42
- add\_command\_line\_sys\_path() (in module photogrammetry\_importer.preferences.dependency), 57
- add\_command\_line\_sys\_path\_if\_necessary() (in module photogrammetry\_importer.preferences.dependency), 57
- add\_depth\_maps\_as\_point\_cloud (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38
- add\_empty() (in module photogrammetry\_importer.blender\_utility.object\_utility), 32
- add\_image\_plane\_emission (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38
- add\_image\_planes (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38
- add\_mesh\_color\_emission (photogrammetry\_importer.importers.mesh\_importer.MeshImporter attribute), 41
- add\_mesh\_to\_point\_geometry\_nodes (photogrammetry\_importer.importers.point\_importer.PointImporter attribute), 42
- add\_mesh\_vertex\_color\_material() (in module photogrammetry\_importer.importers.mesh\_utility), 42
- add\_multi\_line\_label() (in module photogrammetry\_importer.utility.ui\_utility), 64
- add\_obj() (in module photogrammetry\_importer.blender\_utility.object\_utility), 32
- add\_points\_as\_mesh\_object (photogrammetry\_importer.importers.point\_importer.PointImporter attribute), 42
- add\_points\_as\_mesh\_vertices() (in module photogrammetry\_importer.importers.point\_utility), 43
- add\_points\_as\_object\_with\_particle\_system() (in module photogrammetry\_importer.importers.point\_utility), 43
- add\_points\_to\_point\_cloud\_handle (photogrammetry\_importer.importers.point\_importer.PointImporter attribute), 42
- AddonPreferences (class in photogrammetry\_importer.preferences.addon\_preferences), 56
- adjust\_clipping\_distance (photogrammetry\_importer.operators.general\_options.GeneralOptions attribute), 46
- adjust\_render\_settings (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39

adjust\_render\_settings\_if\_possible() (in module photogrammetry\_importer.importers.camera\_utility), 40  
 animation\_frame\_source (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39  
 apply\_general\_options() (photogrammetry\_importer.operators.general\_options.GeneralOptions method), 46  
**B**  
 bl\_category (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel attribute), 55  
 bl\_description (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderAnimationPanel attribute), 53  
 bl\_description (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderImagePanel attribute), 53  
 bl\_description (photogrammetry\_importer.panels.render\_operators.SaveOpenGLRenderImagePanel attribute), 53  
 bl\_description (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotAnimationPanel attribute), 54  
 bl\_description (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImagePanel attribute), 54  
 bl\_description (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImagePanel attribute), 54  
 bl\_description (photogrammetry\_importer.preferences.dependency.InstallOptionalDependenciesOperator attribute), 58  
 bl\_description (photogrammetry\_importer.preferences.dependency.UninstallOptionalDependenciesOperator attribute), 59  
 bl\_idname (photogrammetry\_importer.operators.colmap\_export\_op.ExportColmapOperator attribute), 45  
 bl\_idname (photogrammetry\_importer.operators.colmap\_import\_op.ImportColmapOperator attribute), 45  
 bl\_idname (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
 bl\_idname (photogrammetry\_importer.operators.mve\_import\_op.ImportMVEOperator attribute), 48  
 bl\_idname (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator attribute), 48  
 bl\_idname (photogrammetry\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator attribute), 49  
 bl\_idname (photogrammetry\_importer.operators.opensfm\_import\_op.ImportOpenSfMOperator attribute), 50  
 bl\_idname (photogrammetry\_importer.operators.point\_data\_import\_op.ImportPointDataOperator attribute), 51  
 bl\_idname (photogrammetry\_importer.operators.visualsfm\_export\_op.ExportVisualSfMOperator attribute), 51  
 bl\_idname (photogrammetry\_importer.operators.visualsfm\_import\_op.ImportVisualSfMOperator attribute), 52  
 bl\_idname (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderAnimationPanel attribute), 53  
 bl\_idname (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderImagePanel attribute), 53  
 bl\_idname (photogrammetry\_importer.panels.render\_operators.SaveOpenGLRenderImagePanel attribute), 53  
 bl\_idname (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotAnimationPanel attribute), 54  
 bl\_idname (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImagePanel attribute), 54  
 bl\_idname (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel attribute), 55  
 bl\_idname (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 56  
 bl\_idname (photogrammetry\_importer.preferences.addon\_preferences.ResetImportOptionsOperator attribute), 57  
 bl\_idname (photogrammetry\_importer.preferences.addon\_preferences.UpdateImporterExportOptionsOperator attribute), 57  
 bl\_idname (photogrammetry\_importer.preferences.dependency.InstallOptionalDependenciesOperator attribute), 58  
 bl\_idname (photogrammetry\_importer.preferences.dependency.UninstallOptionalDependenciesOperator attribute), 59  
 bl\_info (in module photogrammetry\_importer), 64  
 bl\_label (photogrammetry\_importer.operators.colmap\_export\_op.ExportColmapOperator attribute), 45  
 bl\_label (photogrammetry\_importer.operators.colmap\_import\_op.ImportColmapOperator attribute), 45  
 bl\_label (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator attribute), 48  
 bl\_label (photogrammetry\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator attribute), 49  
 bl\_label (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47

bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.mve\_import\_op.ImportMVEOperator try\_importer.operators.colmap\_import\_op.ImportColmapOperato  
 attribute), 48 attribute), 45  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.open3d\_import\_op.ImportOpen3DOperator try\_importer.operators.meshroom\_import\_op.ImportMeshroomO  
 attribute), 49 attribute), 47  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator try\_importer.operators.mve\_import\_op.ImportMVEOperator  
 attribute), 49 attribute), 48  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.opensfm\_import\_op.ImportOpenSfMOperator try\_importer.operators.open3d\_import\_op.ImportOpen3DOperato  
 attribute), 50 attribute), 49  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.point\_data\_import\_op.ImportPointDataOperator try\_importer.operators.openmvg\_import\_op.ImportOpenMVGOp  
 attribute), 51 attribute), 49  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.visualsfm\_export\_op.ExportVisualSfMOperator try\_importer.operators.opensfm\_import\_op.ImportOpenSfMOper  
 attribute), 52 attribute), 50  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.operators.visualsfm\_import\_op.ImportVisualSfMOperator try\_importer.operators.point\_data\_import\_op.ImportPointDataO  
 attribute), 52 attribute), 51  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.panels.render\_operators.ExportOpenGLRenderImageOperator try\_importer.operators.visualsfm\_export\_op.ExportVisualSfMOp  
 attribute), 53 attribute), 52  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.panels.render\_operators.ExportOpenGLRenderImageOperator try\_importer.operators.visualsfm\_import\_op.ImportVisualSfMOp  
 attribute), 53 attribute), 52  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.panels.render\_operators.SaveOpenGLRenderImageOperator try\_importer.preferences.dependency.InstallOptionalDependencie  
 attribute), 53 attribute), 58  
 bl\_label (photogramme- bl\_options (photogramme-  
 try\_importer.panels.screenshot\_operators.ExportScreenshotImageOperator try\_importer.preferences.dependency.UninstallOptionalDependen  
 attribute), 54 attribute), 59  
 bl\_label (photogramme- bl\_region\_type (photogramme-  
 try\_importer.panels.screenshot\_operators.ExportScreenshotImageOperator try\_importer.panels.view\_3d\_panel.OpenGLPanel  
 attribute), 54 attribute), 55  
 bl\_label (photogramme- bl\_space\_type (photogramme-  
 try\_importer.panels.view\_3d\_panel.OpenGLPanel try\_importer.panels.view\_3d\_panel.OpenGLPanel  
 attribute), 55 attribute), 55  
 bl\_label (photogramme-  
 try\_importer.preferences.addon\_preferences.ResetImportOptionsOperator  
 attribute), 57  
 bl\_label (photogramme- Camera (class in photogramme-  
 try\_importer.preferences.addon\_preferences.UpdateCameraExtent try\_importer.types.camera), 60  
 attribute), 57 camera\_extent (photogramme-  
 try\_importer.importers.camera\_importer.CameraImporter  
 attribute), 39  
 bl\_label (photogramme-  
 try\_importer.preferences.dependency.InstallOptionalDependenciesOperator (class in photogramme-  
 attribute), 58 try\_importer.importers.camera\_importer),  
 bl\_label (photogramme- 37  
 try\_importer.preferences.dependency.UninstallOptionalDependenciesOperator (photogramme-  
 attribute), 59 try\_importer.importers.point\_importer.PointImporter  
 bl\_options (photogramme- attribute), 42  
 try\_importer.operators.colmap\_export\_op.ExportColmapOperator check\_radial\_distortion() (in module photogram-  
 attribute), 45 metry\_importer.file\_handlers.utility), 36

|                                                        |                                                                                        |                                              |                                                                                                |
|--------------------------------------------------------|----------------------------------------------------------------------------------------|----------------------------------------------|------------------------------------------------------------------------------------------------|
| <code>colmap_exporter_bool</code>                      | (photogrammetry_importer.preferences.addon_preferences.AddonPreferences attribute), 56 | <code>delete_anchor()</code>                 | (photogrammetry_importer.opengl.draw_manager.DrawManager method), 44                           |
| <code>colmap_importer_bool</code>                      | (photogrammetry_importer.preferences.addon_preferences.AddonPreferences attribute), 56 | <code>dependency_package_name</code>         | (photogrammetry_importer.preferences.dependency.InstallOptionalDependencies attribute), 59     |
| <code>ColmapFileHandler</code>                         | (class in photogrammetry_importer.file_handlers.colmap_file_handler), 33               | <code>dependency_package_name</code>         | (photogrammetry_importer.preferences.dependency.UninstallOptionalDependencies attribute), 59   |
| <code>compute_calibration_mat()</code>                 | (photogrammetry_importer.types.camera.Camera static method), 61                        | <code>DependencyStatus</code>                | (class in photogrammetry_importer.preferences.dependency), 57                                  |
| <code>compute_camera_matrix_world()</code>             | (in module photogrammetry_importer.importers.camera_utility), 40                       | <code>depth_map_default_color</code>         | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38               |
| <code>compute_principal_point_shift()</code>           | (in module photogrammetry_importer.importers.camera_utility), 40                       | <code>depth_map_display_sparsity</code>      | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38               |
| <code>consider_missing_cameras_during_animation</code> | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 39       | <code>depth_map_id_or_name_str</code>        | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38               |
| <code>convert_cam_coords_to_world_coords()</code>      | (photogrammetry_importer.types.camera.Camera method), 62                               | <code>DEPTH_MAP_WRT_CANONICAL_VECTORS</code> | (photogrammetry_importer.types.camera.Camera attribute), 60                                    |
| <code>convert_depth_map_to_cam_coords()</code>         | (photogrammetry_importer.types.camera.Camera method), 62                               | <code>DEPTH_MAP_WRT_UNIT_VECTORS</code>      | (photogrammetry_importer.types.camera.Camera attribute), 60                                    |
| <code>convert_depth_map_to_world_coords()</code>       | (photogrammetry_importer.types.camera.Camera method), 62                               | <code>directory</code>                       | (photogrammetry_importer.operators.colmap_export_op.ExportColmapOperator attribute), 45        |
| <code>create_geometry_nodes_node_group()</code>        | (in module photogrammetry_importer.importers.point_utility), 43                        | <code>directory</code>                       | (photogrammetry_importer.operators.colmap_import_op.ImportColmapOperator attribute), 45        |
| <code>create_points()</code>                           | (photogrammetry_importer.types.point.Point static method), 62                          | <code>directory</code>                       | (photogrammetry_importer.operators.meshroom_import_op.ImportMeshroomOperator attribute), 47    |
| <b>D</b>                                               |                                                                                        | <code>directory</code>                       | (photogrammetry_importer.operators.mve_import_op.ImportMVEOperator attribute), 48              |
| <code>default_focal_length</code>                      | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38       | <code>directory</code>                       | (photogrammetry_importer.operators.open3d_import_op.ImportOpen3DOperator attribute), 49        |
| <code>default_height</code>                            | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 37       | <code>directory</code>                       | (photogrammetry_importer.operators.openmvg_import_op.ImportOpenMVGOperator attribute), 49      |
| <code>default_pp_x</code>                              | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38       | <code>directory</code>                       | (photogrammetry_importer.operators.opensfm_import_op.ImportOpenSfmOperator attribute), 50      |
| <code>default_pp_y</code>                              | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 38       | <code>directory</code>                       | (photogrammetry_importer.operators.point_data_import_op.ImportPointDataOperator attribute), 51 |
| <code>default_width</code>                             | (photogrammetry_importer.importers.camera_importer.CameraImporter attribute), 37       | <code>directory</code>                       | (photogrammetry_importer.operators.visualsfm_export_op.ExportVisualSfmOperator attribute), 52  |
|                                                        |                                                                                        | <code>directory</code>                       | (photogrammetry-                                                                               |

`try_importer.operators.visualsfm_import_op.ImportVisualSfmOperator`  
 attribute), 52

`draw()` (photogramme-  
`try_importer.operators.colmap_import_op.ImportColmapOperator`  
 method), 46

`draw()` (photogramme-  
`try_importer.operators.meshroom_import_op.ImportMeshroomOperator`  
 method), 48

`draw()` (photogramme-  
`try_importer.operators.mve_import_op.ImportMVEOperator`  
 method), 48

`draw()` (photogramme-  
`try_importer.operators.open3d_import_op.ImportOpen3DOperator`  
 method), 49

`draw()` (photogramme-  
`try_importer.operators.openmvg_import_op.ImportOpenMVGOperator`  
 method), 50

`draw()` (photogramme-  
`try_importer.operators.opensfm_import_op.ImportOpenSfmOperator`  
 method), 50

`draw()` (photogramme-  
`try_importer.operators.open3d_import_op.ImportOpen3DOperator`  
 method), 49

`draw()` (photogramme-  
`try_importer.operators.openmvg_import_op.ImportOpenMVGOperator`  
 method), 49

`draw()` (photogramme-  
`try_importer.operators.opensfm_import_op.ImportOpenSfmOperator`  
 method), 50

`draw()` (photogramme-  
`try_importer.operators.point_data_import_op.ImportPointDataOperator`  
 method), 51

`draw()` (photogramme-  
`try_importer.operators.visualsfm_import_op.ImportVisualSfmOperator`  
 method), 52

`draw()` (photogramme-  
`try_importer.panels.view_3d_panel.OpenGLPanel`  
 method), 56

`draw()` (photogramme-  
`try_importer.operators.opensfm_import_op.ImportOpenSfmOperator`  
 method), 50

`draw()` (photogramme-  
`try_importer.operators.point_data_import_op.ImportPointDataOperator`  
 method), 51

`draw_camera_options()` (photogramme-  
`try_importer.importers.camera_importer.CameraImporter`  
 method), 39

`draw_coords()` (in module `photogramme-try_importer.opengl.utility`), 44

`draw_general_options()` (photogramme-  
`try_importer.operators.general_options.GeneralOptions`  
 method), 46

`draw_mesh_options()` (photogramme-  
`try_importer.importers.mesh_importer.MeshImporter`  
 method), 41

`draw_point_options()` (photogramme-  
`try_importer.importers.point_importer.PointImporter`  
 method), 43

`draw_points()` (in module `photogramme-try_importer.opengl.utility`), 44

`draw_points_with_gpu` (photogramme-  
`try_importer.importers.point_importer.PointImporter`  
 attribute), 42

`DrawManager` (class in `photogramme-try_importer.opengl.draw_manager`), 44

`execute()` (photogramme-  
`try_importer.operators.colmap_export_op.ExportColmapOperator`  
 method), 45

`execute()` (photogramme-  
`try_importer.operators.colmap_import_op.ImportColmapOperator`  
 method), 45

`execute()` (photogramme-  
`try_importer.operators.export_op.ExportOperator`  
 method), 46

`execute()` (photogramme-  
`try_importer.operators.import_op.ImportOperator`  
 method), 47

`execute()` (photogramme-  
`try_importer.operators.meshroom_import_op.ImportMeshroomOperator`  
 method), 48

`execute()` (photogramme-  
`try_importer.operators.mve_import_op.ImportMVEOperator`  
 method), 48

`execute()` (photogramme-  
`try_importer.operators.open3d_import_op.ImportOpen3DOperator`  
 method), 49

`execute()` (photogramme-  
`try_importer.operators.openmvg_import_op.ImportOpenMVGOperator`  
 method), 49

`execute()` (photogramme-  
`try_importer.operators.opensfm_import_op.ImportOpenSfmOperator`  
 method), 50

`execute()` (photogramme-  
`try_importer.operators.point_data_import_op.ImportPointDataOperator`  
 method), 51

`execute()` (photogramme-  
`try_importer.operators.visualsfm_export_op.ExportVisualSfmOperator`  
 method), 52

`execute()` (photogramme-  
`try_importer.operators.visualsfm_import_op.ImportVisualSfmOperator`  
 method), 52

`execute()` (photogramme-  
`try_importer.panels.render_operators.ExportOpenGLRenderAnimation`  
 method), 54

`execute()` (photogramme-  
`try_importer.panels.render_operators.ExportOpenGLRenderImage`  
 method), 53

`execute()` (photogramme-  
`try_importer.panels.render_operators.SaveOpenGLRenderImage`  
 method), 53

`execute()` (photogramme-  
`try_importer.panels.screenshot_operators.ExportScreenshotAnimation`  
 method), 54

`execute()` (photogramme-  
`try_importer.panels.screenshot_operators.ExportScreenshotImage`  
 method), 54

`execute()` (photogramme-  
`try_importer.preferences.addon_preferences.ResetImportOptions`  
 method), 54



method), 57

execute() (photogrammetry\_importer.preferences.addon\_preferences.UpdateImporterPreferencesOperator module method), 57

execute() (photogrammetry\_importer.preferences.dependency.InstallOptionalDependenciesOperator module method), 59

execute() (photogrammetry\_importer.preferences.dependency.UninstallOptionalDependenciesOperator module method), 59

ExportColmapOperator (class in photogrammetry\_importer.operators.colmap\_export\_op), 45

ExportOpenGLRenderAnimationOperator (class in photogrammetry\_importer.panels.render\_operators), 53

ExportOpenGLRenderImageOperator (class in photogrammetry\_importer.panels.render\_operators), 53

ExportOperator (class in photogrammetry\_importer.operators.export\_op), 46

ExportScreenshotAnimationOperator (class in photogrammetry\_importer.panels.screenshot\_operators), 54

ExportScreenshotImageOperator (class in photogrammetry\_importer.panels.screenshot\_operators), 54

ExportVisualSfmOperator (class in photogrammetry\_importer.operators.visualsfm\_export\_op), 51

**F**

filename\_ext (photogrammetry\_importer.operators.colmap\_export\_op.ExportColmapOperator module attribute), 45

filename\_ext (photogrammetry\_importer.operators.visualsfm\_export\_op.ExportVisualSfmOperator module attribute), 52

filename\_ext (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderAnimationOperator module attribute), 53

filename\_ext (photogrammetry\_importer.panels.render\_operators.ExportOpenGLRenderImageOperator module attribute), 53

filename\_ext (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotAnimationOperator module attribute), 54

filename\_ext (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImageOperator module attribute), 54

filepath (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator module attribute), 47

filepath (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator module attribute), 49

filepath (photogrammetry\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator module attribute), 49

filepath (photogrammetry\_importer.operators.opensfm\_import\_op.ImportOpenSfmOperator module attribute), 50

filepath (photogrammetry\_importer.operators.point\_data\_import\_op.ImportPointDataOperator module attribute), 51

filepath (photogrammetry\_importer.operators.visualsfm\_import\_op.ImportVisualSfmOperator module attribute), 52

files (photogrammetry\_importer.operators.colmap\_export\_op.ExportColmapOperator module attribute), 45

files (photogrammetry\_importer.operators.visualsfm\_export\_op.ExportVisualSfmOperator module attribute), 52

filter\_glob (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator module attribute), 47

filter\_glob (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator module attribute), 49

filter\_glob (photogrammetry\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator module attribute), 49

filter\_glob (photogrammetry\_importer.operators.opensfm\_import\_op.ImportOpenSfmOperator module attribute), 50

filter\_glob (photogrammetry\_importer.operators.point\_data\_import\_op.ImportPointDataOperator module attribute), 51

filter\_glob (photogrammetry\_importer.operators.visualsfm\_export\_op.ExportVisualSfmOperator module attribute), 52

filter\_glob (photogrammetry\_importer.operators.visualsfm\_import\_op.ImportVisualSfmOperator module attribute), 52

**G**

GeneralOptions (class in photogrammetry\_importer.panels.render\_operators.general\_options), 46

get\_4x4\_cam\_to\_world\_mat() (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotAnimationOperator module method), 62

get\_absolute\_fp() (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotImageOperator module method), 60

get\_additional\_command\_line\_sys\_path() (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator module method), 47

`try_importer.preferences.dependency`), 57  
`get_calibration_mat()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_camera_center()` (`photogrammetry_importer.types.camera.Camera` method), 62  
`get_centered_points()` (`photogrammetry_importer.types.point.Point` static method), 62  
`get_coords_and_colors()` (`photogrammetry_importer.opengl.draw_manager.DrawManager` method), 44  
`get_default_image_path()` (`photogrammetry_importer.operators.import_op.ImportOperator` method), 46  
`get_dependencies()` (`photogrammetry_importer.preferences.dependency.OptionalDependencyManager` method), 58  
`get_depth_map()` (`photogrammetry_importer.types.camera.Camera` method), 62  
`get_depth_map_fp()` (`photogrammetry_importer.types.camera.Camera` method), 62  
`get_draw_callback_handler()` (`photogrammetry_importer.opengl.draw_manager.DrawManager` method), 44  
`get_elapsed_time()` (`photogrammetry_importer.utility.timing_utility.StopWatch` method), 64  
`get_field_of_view()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_file_name()` (`photogrammetry_importer.types.camera.Camera` method), 60  
`get_file_paths_in_dir()` (in module `photogrammetry_importer.utility.os_utility`), 63  
`get_focal_length()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_image_file_paths_in_dir()` (in module `photogrammetry_importer.utility.os_utility`), 63  
`get_object_animation_indices()` (in module `photogrammetry_importer.blender_utility.retrieval_utility`), 32  
`get_package_info()` (`photogrammetry_importer.preferences.dependency.DependencyManager` method), 58  
`get_package_info()` (`photogrammetry_importer.preferences.dependency.PipManager` method), 58  
`get_panoiramic_type()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_principal_point()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_relative_fp()` (`photogrammetry_importer.types.camera.Camera` method), 60  
`get_rotation_as_quaternion()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_rotation_as_rotation_mat()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_scene_animation_indices()` (in module `photogrammetry_importer.blender_utility.retrieval_utility`), 32  
`get_selected_camera()` (in module `photogrammetry_importer.blender_utility.retrieval_utility`), 32  
`get_selected_cameras_and_vertices_of_meshes()` (`photogrammetry_importer.operators.export_op.ExportOperator` method), 46  
`get_selected_empty()` (in module `photogrammetry_importer.blender_utility.retrieval_utility`), 32  
`get_selected_object()` (in module `photogrammetry_importer.blender_utility.retrieval_utility`), 32  
`get_singleton()` (`photogrammetry_importer.opengl.draw_manager.DrawManager` class method), 44  
`get_singleton()` (`photogrammetry_importer.preferences.dependency.OptionalDependencyManager` class method), 58  
`get_singleton()` (`photogrammetry_importer.preferences.dependency.PipManager` class method), 58  
`get_subdirs()` (in module `photogrammetry_importer.utility.os_utility`), 63  
`get_translation_vec()` (`photogrammetry_importer.types.camera.Camera` method), 61  
`get_undistorted_absolute_fp()` (`photogrammetry_importer.types.camera.Camera` method), 60  
`get_undistorted_file_name()` (`photogrammetry_importer.types.camera.Camera` method), 60  
`get_undistorted_relative_fp()` (`photogrammetry_importer.types.camera.Camera` method),

60  
 get\_viz\_point\_size() (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings method), 41  
 method), 55  
**H**  
 has\_focal\_length() (photogrammetry\_importer.types.camera.Camera method), 61  
 has\_intrinsics() (photogrammetry\_importer.types.camera.Camera method), 61  
 has\_principal\_point() (photogrammetry\_importer.types.camera.Camera method), 61  
 has\_undistorted\_absolute\_fp() (photogrammetry\_importer.types.camera.Camera method), 60  
**I**  
 image\_dp (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 37  
 image\_fp\_items (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 37  
 image\_fp\_type (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 37  
 IMAGE\_FP\_TYPE\_ABSOLUTE (photogrammetry\_importer.types.camera.Camera attribute), 60  
 IMAGE\_FP\_TYPE\_NAME (photogrammetry\_importer.types.camera.Camera attribute), 60  
 IMAGE\_FP\_TYPE\_RELATIVE (photogrammetry\_importer.types.camera.Camera attribute), 60  
 image\_plane\_transparency (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38  
 ImageFileHandler (class in photogrammetry\_importer.file\_handlers.image\_file\_handler), 33  
 import\_cameras (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 37  
 import\_mesh (photogrammetry\_importer.importers.mesh\_importer.MeshImporter attribute), 41  
 import\_photogrammetry\_cameras() (photogrammetry\_importer.importers.camera\_importer.CameraImporter method), 40  
 import\_photogrammetry\_mesh() (photogrammetry\_importer.importers.mesh\_importer.MeshImporter method), 41  
 import\_photogrammetry\_points() (photogrammetry\_importer.importers.point\_importer.PointImporter method), 43  
 import\_points (photogrammetry\_importer.importers.point\_importer.PointImporter attribute), 42  
 ImportColmapOperator (class in photogrammetry\_importer.operators.colmap\_import\_op), 45  
 ImportMeshroomOperator (class in photogrammetry\_importer.operators.meshroom\_import\_op), 47  
 ImportMVEOperator (class in photogrammetry\_importer.operators.mve\_import\_op), 48  
 ImportOpen3DOperator (class in photogrammetry\_importer.operators.open3d\_import\_op), 48  
 ImportOpenMVGOperator (class in photogrammetry\_importer.operators.openmvg\_import\_op), 49  
 ImportOpenSfMOperator (class in photogrammetry\_importer.operators.opensfm\_import\_op), 50  
 ImportOperator (class in photogrammetry\_importer.operators.import\_op), 46  
 ImportPointDataOperator (class in photogrammetry\_importer.operators.point\_data\_import\_op), 51  
 ImportVisualSfmOperator (class in photogrammetry\_importer.operators.visualsfm\_import\_op), 52  
 initialize\_options\_from\_addon\_preferences() (photogrammetry\_importer.operators.import\_op.ImportOperator method), 46  
 install() (photogrammetry\_importer.preferences.dependency.OptionalDependency method), 58  
 install\_dependencies() (photogrammetry\_importer.preferences.dependency.OptionalDependencyManager method), 58  
 install\_pip() (photogrammetry\_importer.preferences.dependency.PipManager method), 58  
 InstallOptionalDependenciesOperator (class in photogrammetry\_importer.preferences.dependency), 58  
 interpolation\_items (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39



interpolation\_type (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39  
 invert\_y\_and\_z\_axis() (in module photogrammetry\_importer.importers.camera\_utility), 40  
 invoke() (photogrammetry\_importer.operators.colmap\_import\_op.ImportColmapOperator method), 46  
 invoke() (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator method), 48  
 invoke() (photogrammetry\_importer.operators.mve\_import\_op.ImportMVEOperator method), 48  
 invoke() (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator method), 49  
 invoke() (photogrammetry\_importer.operators.openmvg\_import\_op.ImportOpenMVGOperator method), 50  
 invoke() (photogrammetry\_importer.operators.opensfm\_import\_op.ImportOpenSfMOperator method), 50  
 invoke() (photogrammetry\_importer.operators.point\_data\_import\_op.ImportPointDataOperator method), 51  
 invoke() (photogrammetry\_importer.operators.visualsfm\_import\_op.ImportVisualSfMOperator method), 52  
 is\_float() (in module photogrammetry\_importer.utility.type\_utility), 64  
 is\_int() (in module photogrammetry\_importer.utility.type\_utility), 64  
 is\_panoramic() (photogrammetry\_importer.types.camera.Camera method), 61  
**L**  
 log\_report() (in module photogrammetry\_importer.blender\_utility.logging\_utility), 32  
**M**  
 mesh\_node\_items (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
 mesh\_node\_number (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
 mesh\_node\_type (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
 MeshImporter (class in photogrammetry\_importer.importers.mesh\_importer), 42

42 photogrammetry\_importer.types.point, 62  
 photogrammetry\_importer.importers.point\_utility, 62  
 43 photogrammetry\_importer.utility.developer\_utility,  
 photogrammetry\_importer.opengl, 44 63  
 photogrammetry\_importer.opengl.draw\_manager, photogrammetry\_importer.utility.os\_utility,  
 44 63  
 photogrammetry\_importer.opengl.utility, photogrammetry\_importer.utility.timing\_utility,  
 44 64  
 photogrammetry\_importer.operators, 45 photogrammetry\_importer.utility.type\_utility,  
 photogrammetry\_importer.operators.colmap\_export\_op, 64  
 45 photogrammetry\_importer.utility.ui\_utility,  
 photogrammetry\_importer.operators.colmap\_import\_op, 64  
 45 modules (in module photogrammetry\_importer), 64  
 photogrammetry\_importer.operators.export\_op, mve\_importer\_bool (photogramme-  
 46 try\_importer.preferences.addon\_preferences.AddonPreferences  
 photogrammetry\_importer.operators.general\_options, attribute), 56  
 46 MVEFileHandler (class in photogramme-  
 photogrammetry\_importer.operators.import\_op, try\_importer.file\_handlers.mve\_file\_handler),  
 46 34  
 photogrammetry\_importer.operators.meshroom\_import\_op,  
 47 **N**  
 photogrammetry\_importer.operators.mve\_import\_op, number\_interpolation\_frames (photogramme-  
 48 try\_importer.importers.camera\_importer.CameraImporter  
 photogrammetry\_importer.operators.open3d\_import\_op, attribute), 39  
 48  
 photogrammetry\_importer.operators.openmvg\_import\_op,  
 49 **O**  
 photogrammetry\_importer.operators.opensfm\_import\_op, only\_3d\_view (photogramme-  
 50 try\_importer.panels.view\_3d\_panel.OpenGLPanelSettings  
 attribute), 55  
 photogrammetry\_importer.operators.point\_data\_import\_op, open3d\_importer\_bool (photogramme-  
 51 try\_importer.preferences.addon\_preferences.AddonPreferences  
 photogrammetry\_importer.operators.utility, attribute), 56  
 51 Open3DFileHandler (class in photogramme-  
 photogrammetry\_importer.operators.visualsfm\_export\_op, try\_importer.file\_handlers.open3D\_file\_handler),  
 51 34  
 photogrammetry\_importer.operators.visualsfm\_import\_op, OpenGLPanel (class in photogramme-  
 52 try\_importer.panels.view\_3d\_panel), 55  
 photogrammetry\_importer.panels, 53 OpenGLPanelSettings (class in photogramme-  
 photogrammetry\_importer.panels.render\_operators, try\_importer.panels.view\_3d\_panel), 55  
 53 openmvg\_importer\_bool (photogramme-  
 photogrammetry\_importer.panels.screenshot\_operators, try\_importer.preferences.addon\_preferences.AddonPreferences  
 54 attribute), 56  
 photogrammetry\_importer.panels.view\_3d\_panel, OpenMVGJSONFileHandler (class in photogramme-  
 55 try\_importer.file\_handlers.openmvg\_json\_file\_handler),  
 photogrammetry\_importer.preferences, 56 35  
 photogrammetry\_importer.preferences.addon\_preferences, open3d\_importer\_bool (photogramme-  
 56 try\_importer.preferences.addon\_preferences.AddonPreferences  
 photogrammetry\_importer.preferences.dependency, attribute), 56  
 57 OpenSfMJSONFileHandler (class in photogramme-  
 photogrammetry\_importer.registration, 59 try\_importer.file\_handlers.opensfm\_json\_file\_handler),  
 photogrammetry\_importer.registration.registration, 35  
 59 **O**  
 photogrammetry\_importer.types, 60 OptionalDependency (class in photogramme-  
 photogrammetry\_importer.types.camera, 60 try\_importer.preferences.dependency), 58

|                                                                                                                                               |                                                                              |
|-----------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------|
| OptionalDependencyManager (class in photogrammetry_importer.preferences.dependency), 58                                                       | photogrammetry_importer.blender_utility module, 31                           |
| <b>P</b>                                                                                                                                      | photogrammetry_importer.blender_utility.image_utility module, 32             |
| panoramic_type_equirectangular (photogrammetry_importer.types.camera.Camera attribute), 60                                                    | photogrammetry_importer.blender_utility.logging_utility module, 32           |
| parse_colmap_folder() (photogrammetry_importer.file_handlers.colmap_file_handler.ColmapFileHandler static method), 33                         | photogrammetry_importer.blender_utility.object_utility module, 32            |
| parse_colmap_model_folder() (photogrammetry_importer.file_handlers.colmap_file_handler.ColmapFileHandler static method), 33                   | photogrammetry_importer.blender_utility.retrieval_utility module, 32         |
| parse_meshroom_mg_file() (photogrammetry_importer.file_handlers.meshroom_file_handler.MeshroomFileHandler class method), 34                   | photogrammetry_importer.file_handlers module, 33                             |
| parse_meshroom_file() (photogrammetry_importer.file_handlers.meshroom_file_handler.MeshroomFileHandler class method), 34                      | photogrammetry_importer.file_handlers.colmap_file_handler module, 33         |
| parse_meshroom_sfm_file() (photogrammetry_importer.file_handlers.meshroom_file_handler.MeshroomFileHandler class method), 33                  | photogrammetry_importer.file_handlers.image_file_handler module, 33          |
| parse_meta() (photogrammetry_importer.file_handlers.mve_file_handler.MVEFileHandler static method), 34                                        | photogrammetry_importer.file_handlers.meshroom_file_handler module, 33       |
| parse_mve_workspace() (photogrammetry_importer.file_handlers.mve_file_handler.MVEFileHandler static method), 34                               | photogrammetry_importer.file_handlers.meshroom_file_handler module, 33       |
| parse_open3d_file() (photogrammetry_importer.file_handlers.open3D_file_handler.Open3DFileHandler static method), 34                           | photogrammetry_importer.file_handlers.mve_file_handler module, 34            |
| parse_openmvg_file() (photogrammetry_importer.file_handlers.openmvg_json_file_handler.OpenmvgJSONFileHandler static method), 35               | photogrammetry_importer.file_handlers.open3D_file_handler module, 34         |
| parse_opensfm_file() (photogrammetry_importer.file_handlers.opensfm_json_file_handler.OpensfmJSONFileHandler static method), 35               | photogrammetry_importer.file_handlers.openmvg_json_file_handler module, 35   |
| parse_point_data_file() (photogrammetry_importer.file_handlers.point_data_file_handler.PointDataFileHandler static method), 35                | photogrammetry_importer.file_handlers.opensfm_json_file_handler module, 35   |
| parse_synth_out() (photogrammetry_importer.file_handlers.mve_file_handler.MVEFileHandler static method), 34                                   | photogrammetry_importer.file_handlers.point_data_file_handler module, 35     |
| parse_transformation_folder() (photogrammetry_importer.file_handlers.transformation_file_handler.TransformationFileHandler static method), 36 | photogrammetry_importer.file_handlers.transformation_file_handler module, 36 |
| parse_views() (photogrammetry_importer.file_handlers.mve_file_handler.MVEFileHandler static method), 34                                       | photogrammetry_importer.file_handlers.utility module, 36                     |
| parse_visualsfm_file() (photogrammetry_importer.file_handlers.visualsfm_file_handler.VisualsfmFileHandler class method), 36                   | photogrammetry_importer.file_handlers.visualsfm_file_handler module, 36      |
| photogrammetry_importer module, 31                                                                                                            | photogrammetry_importer.importers module, 36                                 |
|                                                                                                                                               | photogrammetry_importer.importers.camera_animation_utility module, 36        |
|                                                                                                                                               | photogrammetry_importer.importers.camera_importer module, 37                 |
|                                                                                                                                               | photogrammetry_importer.importers.camera_utility module, 40                  |
|                                                                                                                                               | photogrammetry_importer.importers.mesh_importer module, 41                   |
|                                                                                                                                               | photogrammetry_importer.importers.mesh_utility module, 42                    |
|                                                                                                                                               | photogrammetry_importer.importers.point_importer module, 42                  |
|                                                                                                                                               | photogrammetry_importer.importers.point_utility module, 43                   |
|                                                                                                                                               | photogrammetry_importer.importers.opengl module, 44                          |
|                                                                                                                                               | photogrammetry_importer.opengl.draw_manager module, 44                       |

|                                                                            |                                                                                                                         |
|----------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------|
| photogrammetry_importer.opengl.utility<br>module, 44                       | photogrammetry_importer.types.point<br>module, 62                                                                       |
| photogrammetry_importer.operators<br>module, 45                            | photogrammetry_importer.utility<br>module, 63                                                                           |
| photogrammetry_importer.operators.colmap_export_operator<br>module, 45     | photogrammetry_importer.utility.developer_utility<br>module, 63                                                         |
| photogrammetry_importer.operators.colmap_import_operator<br>module, 45     | photogrammetry_importer.utility.os_utility<br>module, 63                                                                |
| photogrammetry_importer.operators.export_operator<br>module, 46            | photogrammetry_importer.utility.timing_utility<br>module, 64                                                            |
| photogrammetry_importer.operators.general_options<br>module, 46            | photogrammetry_importer.utility.type_utility<br>module, 64                                                              |
| photogrammetry_importer.operators.import_operator<br>module, 46            | photogrammetry_importer.utility.ui_utility<br>module, 64                                                                |
| photogrammetry_importer.operators.meshroom_import_operator<br>module, 47   | PointImage (photogramme-<br>try_importer.file_handlers.image_file_handler.ImageFileHandler<br>attribute), 33            |
| photogrammetry_importer.operators.mve_import_operator<br>module, 48        | PipManager (class in photogramme-<br>try_importer.preferences.dependency), 58                                           |
| photogrammetry_importer.operators.open3d_import_operator<br>module, 48     | Point (class in photogrammetry_importer.types.point),<br>62                                                             |
| photogrammetry_importer.operators.openmvg_import_operator<br>module, 49    | point_cloud_display_sparsity (photogramme-<br>try_importer.importers.point_importer.PointImporter<br>attribute), 42     |
| photogrammetry_importer.operators.opensfm_import_operator<br>module, 50    | point_data_importer_bool (photogramme-<br>try_importer.preferences.addon_preferences.AddonPreferences<br>attribute), 56 |
| photogrammetry_importer.operators.point_data_import_operator<br>module, 51 | point_radius (photogramme-<br>try_importer.importers.point_importer.PointImporter<br>attribute), 42                     |
| photogrammetry_importer.operators.utility<br>module, 51                    | point_size (photogramme-<br>try_importer.importers.point_importer.PointImporter<br>attribute), 42                       |
| photogrammetry_importer.operators.visualsfm_export_operator<br>module, 51  | point_subdivisions (photogramme-<br>try_importer.importers.point_importer.PointImporter<br>attribute), 43               |
| photogrammetry_importer.operators.visualsfm_import_operator<br>module, 52  | PointDataFileHandler (class in photogramme-<br>try_importer.file_handlers.point_data_file_handler),<br>35               |
| photogrammetry_importer.panels<br>module, 53                               | PointImporter (class in photogramme-<br>try_importer.importers.point_importer),<br>42                                   |
| photogrammetry_importer.panels.render_operators<br>module, 53              | poll() (photogramme-<br>try_importer.panels.render_operators.ExportOpenGLRenderAnim<br>class method), 54                |
| photogrammetry_importer.panels.screenshot_operators<br>module, 54          | poll() (photogramme-<br>try_importer.panels.render_operators.ExportOpenGLRenderImage<br>class method), 53               |
| photogrammetry_importer.panels.view_3d_panel<br>module, 55                 | poll() (photogramme-<br>try_importer.panels.render_operators.SaveOpenGLRenderImage<br>class method), 53                 |
| photogrammetry_importer.preferences<br>module, 56                          | poll() (photogramme-<br>try_importer.panels.screenshot_operators.ExportScreenshotAnim<br>class method), 54              |
| photogrammetry_importer.preferences.addon_preferences<br>module, 56        |                                                                                                                         |
| photogrammetry_importer.preferences.dependency<br>module, 57               |                                                                                                                         |
| photogrammetry_importer.registration<br>module, 59                         |                                                                                                                         |
| photogrammetry_importer.registration.registration<br>module, 59            |                                                                                                                         |
| photogrammetry_importer.types<br>module, 60                                |                                                                                                                         |
| photogrammetry_importer.types.camera<br>module, 60                         |                                                                                                                         |

poll() (photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotOperator.render\_opengl\_image() (in module photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotOperator), 44  
class method), 54  
reorganize\_undistorted\_images (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39

poll() (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel attribute), 39  
class method), 55  
reset\_import\_options() (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 57  
reset\_time() (photogrammetry\_importer.utility.timing\_utility.StopWatch method), 64

prepare\_node\_number (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47

## Q

quaternion\_to\_rotation\_matrix() (photogrammetry\_importer.types.camera.Camera static method), 62  
ResetImportOptionsOperator (class in photogrammetry\_importer.preferences.addon\_preferences), 57

## R

rotation\_matrix\_to\_quaternion() (photogrammetry\_importer.types.camera.Camera static method), 62

read\_depth\_map() (photogrammetry\_importer.file\_handlers.mve\_file\_handler.MVEFileHandler static method), 34

read\_image\_size() (photogrammetry\_importer.file\_handlers.image\_file\_handler.ImageFileHandler class method), 33

reconstruction\_number (photogrammetry\_importer.operators.opensfm\_import\_op.ImportOpensfmOperator attribute), 50

redraw\_points() (in module photogrammetry\_importer.opengl.utility), 44

register() (in module photogrammetry\_importer), 64

register() (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel class method), 55  
(photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences class method), 56

register\_exporters() (photogrammetry\_importer.registration.registration.Registration class method), 59

register\_importers() (photogrammetry\_importer.registration.registration.Registration class method), 59

register\_points\_draw\_callback() (photogrammetry\_importer.opengl.draw\_manager.DrawManager method), 44

Registration (class in photogrammetry\_importer.registration.registration), 59

remove\_command\_line\_sys\_path() (in module photogrammetry\_importer.preferences.dependency), 57

remove\_rotation\_discontinuities (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39

render\_file\_format (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55

render\_opengl\_image() (in module photogrammetry\_importer.panels.screenshot\_operators.ExportScreenshotOperator), 44

reorganize\_undistorted\_images (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39

reset\_import\_options() (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 57

reset\_time() (photogrammetry\_importer.utility.timing\_utility.StopWatch method), 64

ResetImportOptionsOperator (class in photogrammetry\_importer.preferences.addon\_preferences), 57

rotation\_matrix\_to\_quaternion() (photogrammetry\_importer.types.camera.Camera static method), 62

## S

save\_alpha (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55

save\_images\_to\_disk() (in module photogrammetry\_importer.blender\_utility.image\_utility), 32

save\_point\_size (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55

SaveOpenGLRenderImageOperator (class in photogrammetry\_importer.panels.render\_operators), 53

screenshot\_file\_format (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55

set\_4x4\_cam\_to\_world\_mat() (photogrammetry\_importer.types.camera.Camera method), 62

set\_absolute\_fp() (photogrammetry\_importer.types.camera.Camera method), 60

set\_calibration() (photogrammetry\_importer.types.camera.Camera method), 60

set\_calibration\_mat() (photogrammetry\_importer.types.camera.Camera method), 61

set\_camera\_center\_after\_rotation() (photogrammetry\_importer.types.camera.Camera method), 61

set\_camera\_translation\_vector\_after\_rotation() (photogrammetry\_importer.types.camera.Camera method), 61



`set_depth_map_callback()` (photogrammetry\_importer.types.camera.Camera method), 62  
`set_image_size_for_cameras()` (in module photogrammetry\_importer.operators.utility), 51  
`set_image_size_of_cameras()` (photogrammetry\_importer.importers.camera\_importer.CameraImporter method), 40  
`set_image_size_of_cameras()` (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator method), 49  
`set_image_size_of_cameras()` (photogrammetry\_importer.operators.visualsfm\_import\_op.ImportVisualSfMOperator method), 52  
`set_intrinsics_of_cameras()` (photogrammetry\_importer.importers.camera\_importer.CameraImporter method), 40  
`set_intrinsics_of_cameras()` (photogrammetry\_importer.operators.open3d\_import\_op.ImportOpen3DOperator method), 49  
`set_panoramic_type()` (photogrammetry\_importer.types.camera.Camera method), 61  
`set_principal_point()` (photogrammetry\_importer.types.camera.Camera method), 61  
`set_relative_fp()` (photogrammetry\_importer.types.camera.Camera method), 60  
`set_rotation_with_quaternion()` (photogrammetry\_importer.types.camera.Camera method), 61  
`set_rotation_with_rotation_mat()` (photogrammetry\_importer.types.camera.Camera method), 61  
`set_viz_point_size()` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings method), 55  
`setup_addon_modules()` (in module photogrammetry\_importer.utility.developer\_utility), 63  
`sfm_node_items` (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
`sfm_node_number` (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
`sfm_node_type` (photogrammetry\_importer.operators.meshroom\_import\_op.ImportMeshroomOperator attribute), 47  
`split_points()` (photogrammetry\_importer.types.point.Point static method), 62  
`StopWatch` (class in photogrammetry\_importer.utility.timing\_utility), 64  
`suppress_distortion_warnings` (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 39  
`sys_path_list_str` (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 56  
`TransformationFileHandler` (class in photogrammetry\_importer.file\_handlers.transformation\_file\_handler), 36  
`uninstall()` (photogrammetry\_importer.preferences.dependency.OptionalDependency method), 58  
`uninstall_dependencies()` (photogrammetry\_importer.preferences.dependency.OptionalDependencyManager method), 58  
`UninstallOptionalDependenciesOperator` (class in photogrammetry\_importer.preferences.dependency), 59  
`unregister()` (in module photogrammetry\_importer), 64  
`unregister()` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanel class method), 56  
`unregister()` (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences class method), 57  
`unregister_exporters()` (photogrammetry\_importer.registration.registration.Registration class method), 59  
`unregister_importers()` (photogrammetry\_importer.registration.registration.Registration class method), 59  
`UpdateImporterExporterOperator` (class in photogrammetry\_importer.preferences.addon\_preferences), 57  
`use_camera_keyframes_for_rendering` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55  
`use_camera_keyframes_for_screenshots` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55  
`use_camera_perspective` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55  
`use_default_depth_map_color` (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 38

`use_workspace_images` (photogrammetry\_importer.importers.camera\_importer.CameraImporter attribute), 37

## V

`visible_preferences` (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 56

`visualsfm_exporter_bool` (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 56

`visualsfm_importer_bool` (photogrammetry\_importer.preferences.addon\_preferences.AddonPreferences attribute), 56

`VisualSfMFileHandler` (class in photogrammetry\_importer.file\_handlers.visualsfm\_file\_handler), 36

`viz_point_size` (photogrammetry\_importer.panels.view\_3d\_panel.OpenGLPanelSettings attribute), 55

## W

`write_colmap_model()` (photogrammetry\_importer.file\_handlers.colmap\_file\_handler.ColmapFileHandler static method), 33

`write_visualsfm_file()` (photogrammetry\_importer.file\_handlers.visualsfm\_file\_handler.VisualSfMFileHandler class method), 36